



User Manual and Reference

Version 4.6.3



Table Of Contents

TABLE OF CONTENTS	1
OVERVIEW	11
THE APPLICATION	
Accessing and Using the Manual	11
COMMAND LINE ARGUMENTS	12
PROJECT COMPONENTS	14
Directory Structure	
PROJECT FOLDER	
Project files (nri)	15
SCRIPT AND ASSOCIATED FILES	15
Scrint files (rh)	15
User Interface files (ui)	
Accept files (accepts)	
Asset files (.ussets)	
Munijest jiles (.munijest)	
PROJECT MENU	17
New Project	17
Open	
Save	
Save As	
Recently Opened	
Close	
Project Settings	
Export Project	
Generate Manifests	
Project Settings	
Script Directories	
Scripts	
Templates	
Libraries	19
Stacks	19
Backups	19
Save	19
Script/Method Hot keys	
DATA DIRECTORIES	
Data Directory	20
Images	20
Fonts	20
Materials	20
Textures	20
Shaders	
Folders Not in Use for 2D	
Database	
Host	
Username	
Password	
Driver	
New	
Delete	
TRANSITION MAP	23
Groups	





	Includes	43
	Custom Transfer Method Name	43
	Reorder Object Nodes	43
	tOG Sports	43
	Recently Opened	43
	Reload	43
	Load last undo	44
	Export	44
	Directory	44
	Assets	44
	Save only the assets saved by the script	44
	Save to Directory	44
	Save to zip	45
	Prefix	45
	Revert	45
	Close	45
тс	OOLS MENU	46
	Import	ЛБ
	Fonts	4 0 26
	Geometric Text	40 ЛС
	Geometric Text	40
		40
	Images	40
	Importing movie files	47
	Noto:	47
	NULE	47
	Create Tiviv	47
	Importing assats from other Swift Projects	47
	Importing 7ID files	47
	Screen Grah	40
	Generate Icon	40
	Clean Project	40
	Durnose	18
	Cleaning Your Project	40 19
	Linusod Assots	ла ла
	Koon Lict	
	Performing the operation	ла ла
	Tacting your project	50
		51
	Timina and Derformance	JI 51
	Timing did Feljonnance	51
	Timing Display	51
	Timing Detail	J1
	Time Pace	JI 51
	ΠΠΕ ΔΟΣΕ	52
	Timing Datail	JZ
	Rar araph and Timina Scope	JZ
	Daf gruph and Thining Scope	JZ
	Geometri as Cibes	J2 52
	Traverse SceneGranh Only	55 51
	Grow Lit Shaders	54 51
	Grou Unlit Shadara	54 E 1
	No Der Divol Lighting	54 E Л
	NU FEI FIXEI LIYIIUIIY	54 54
	Ulic Light Rackface On	54 ۲۵
	Ston Taxtura Unloads	54 E Л
	בוסף ובאנטוב טאוטעמג	54



Small Textures Advanced Shader Editor	
HELP MENU	
PREVIEW WINDOW INTERACTION	56
INTERACTION TOOLBAR	
Selection	
Multiple Selection	
Object Interaction	
CONVENTIONS	57
Free	57
Constrained	57
Free movement	
Translation	
Rotation	
Scale Fditing Text	
SCENEGRAPH EDITOR	60
Scenegraph Toolbar	
Find	60
l oggle Basic Editor	60
Object Node Editor	
Move Nodes Up or Down	
Dragaina a Node	
Move the branch:	61
Link to:	61
Copy the attributes:	61
Cancel:	62
RIGHT CLICK CONTEXT MENU	62
Cut	62
Copy	
Paste	
Delete Node [exc subtree]	
Rename	
Add input	63
Toggle lock	63
Group	63
Link	63
Duplicate	63
GRAPHIC AND ASSET TABS	64
GRAPHIC ТАВ	64
Description	
Usage	64
Images Tab	65
Description	65
Usage	65
Fonts Тав	
Description	
PRIMITIVES TAR	
Description	
VideoScreenNode	
Usage	
Interface	68
Clock Node	



Usage	70
Interface	70
Interaction	71
Clock Types	71
Events	71
Notes and Exceptions	72
TICKER AND ROLLER NODES	73
Usage	73
Interface	
Source	
Widget Interface	75
Widget Name	75
Database	
MOS parameter	
Update	
	78
SHDR EDITOR TAB	79
DGEOM EDITOR TAB	81
Triangle and circle DGEOM options	81
Reset values	82
Scale linkage	82
Add Input	82
Add Animator	82
Text Editor Tab	
Editing Text	
Text Markup	
Changing Content using Links	84
Editing Text on Screen	
	ол
Alignment	
Styles	86
LINKS EDITOR TABS	
Data Type Conversion	89
Range Manning	89
Miscellaneous Ontions	
	92
Methods	
Blocks	
TIMELINE TOOLBAR	93
Transport Controls	
Field Counter	94
Zoom	
Creating Animations	
Adding Kevframes	
Selecting Animators	
Editing Animator Durations	95
Moving Animators in time	
Node to scenegraph dragging	
	07
ANIMATORS: PATH TYPE	97
Keyframe points	97
Selecting a keyframe	97
Editing the curve	97
Editing keyframes visually	
Lating kontromos monually	98



Grid sizes	
ANIMATORS: RAMP TYPE	
Editing keyframes visually	
Editing keyframes manually	
ANIMATORS: STEP TYPE	
Editing keyframes visually	
Editing keyframes manually	
ANIMATORS' CYCLIC TYPE	
Editing keyframes visually	
Editing keyframes manually	
Class	
Nodo	
Field	
Reneat	
Delav	
Field Darameter	
IPUTS TAB	
SOLIRCE	
Widget	
Widget	
Display in Stack	
MOS Parameter	
Filter	
Display in Stack	
Database	
Edit SQL	
Database	
Table	
Where	
Column	
Details	
Eval	
Database Statement	
Variable Interpolation	
Script Variable	
Constant	
Scenegraph	
Touch Parameter and Toa Sports	
Command	
Variable Internelation	
Variable Interpolation on Database and Command Inputs	
Default values for interpolation	
Dynamic	
Data Type	
Scenegraph	
Node Name	
Field Name	
Script Value	
Animation	
Animator Node Name	
Method Data	
MethodData Format	
TOG Sports	
SER CODE TAB	
Detault user code	



bringOn	
takeOff	
Changing Input Results using User Code	
ADVANCED SHADER EDITOR	119
Usage	
Saving changes	
Advanced Shader Tab	
Advanced Material Tab	
Diffuse	
Opacity	
Ambient	
Specular	
Emission	
Shininess	
Side	
Advanced Texture Tab	
Texture Image sub-menu	
Video I/P1 through I/P4	
Cube Map Images	
Blending	
Position sub-menu	
Filter sub-menu	
Minification	
Magnification	
Format sub-menu	
Target:	
Texture Cube Map:	12/
Texture SD	
Internal Format:	
Wrapping	
Animation	
Bounce	
Frame Delay:	
Number Loops:	
Information:	
Reset Image:	
Sprites	
Wrapping:	
Repeat:	
Clamp To Edge:	
Animation sub-menu	
Sprites sub-menu	
Audio sub-menu	
Advanced State Tab	
General sub-menu	
Depth Control sub-menu	
Blending sub-menu	
Lighting sub-menu	
Operations sub-menu	
Points sub-menu	
Polygons sub-menu	
Stencil sub-menu	
	400
Overview	139
Terminology	139



Graphic Template	
Page	
Stack	
Method	
Preview	
Object Transition	
Workflow	
Swift Editor	
Playout Editor	
Setup for standalone Playout (with no preview)	
Entering Playout Mode/Interface	142
Playout Toolbar	1/2
1 Draview window	143
1. Fleview Wildow	
2. Control Buttons	
Clear Stack	
Abort	
Load and Save	
Up and Down arrows	
Clear (F11)	
Delete	
Layoff	
3. Stack	
4. Graphic template browser	
5. Method browser	
6. Graphic interfaces	
Operations	
Stacking a graphic.	
Editing a graphic	
Selecting and taking a graphic	148
Rearranging the Stack	
Clearing Stacked Graphics	
Aborting a Graphic	149
Plaving methods	
To view available methods :	
To stack a method :	149
To play a method :	149
Loading and Saving Stacks	150
Stack Looning	150
Page Starks	150
To recall a page stack ·	150
Lavoff to disk	150
Destination Directory	
Destination Directory	
Destination Name	
FUTINAL	
Cue Frames	
Separate Alpha	
Field Kender	
Udd Field Dominance	
Viaeo coaec	
wipeg2	
UNCOMPRESSED+A	
Controlling Multiple Playouts	
Port Number	
Address	
Examining the Scenegraph	



DOCUMENT SUMMARY	155
FURTHER READING	155
APPENDICES	156
1 - RECOMMENDED XDCAM ASSET PREP	
Using ffmpeg from the command line:	
For Movies without embedded audio	
For image sequences	
Using Adobe tools:	
From After Effects Render Queue	
Format	
Audio	
Video Output Module	
From Media Encoder	
Format for clips with no embedded audio	
Disable audio	
Advanced Options	
Field rendering	
For clips that require embedded audio	162
2 - Evaluating movie files	
Why are .tga image sequences supplied at all?	
Why not supply movie files instead of .tga image sequences?	
Recommended video clip formats	
Video clips without alpha	
All with the following specifications:	
Advantages	
Video clips with alpha	
Advantages	
Disadvantages	
Establishing data rates for Quicktime movies	
Establishing data rates for MXF movies	
Establishing the codec used for Quicktime movies	
Establishing the codec used for MXF movies	
Using master and matte movie clips in Swift	
Step 1: Creating a master video clip	
Step 2: Creating a matte image sequence	
Inverting the matte	
Rendering your matte image sequence	
Using ffmpeg to create a matte movie	
Working example	
Open a command prompt at the correct location	
Adding your image sequence	
Image sequence number	
Do T transcouer	
is the data rate of your clip <120mbs/sec but >80mbs/sec?	
3 - SUPPORTED FORMATS	
Input formats	
Input wrappers	
Input Codecs	
Output Formats	
mpg	
avi	
mxt	
mov	
TIV	
tmv	
4 - CUE IVIARGIN	
Adding cueGraphic methods to templates for ICE	



What is the cueGraphic method	
Why use the cueGraphic method	
How to add a cueGraphic method in the 2d editor	
Adding or moving components to the cueGraphic method	
Using cueGraphic method with movie clips	
Preparing the cueGraphic method	
Moving Inputs	
Moving user code	
Saving the graphic	
Setting the Cue margin in ICE Configuration	



Overview

The Application

Swift (previously known as tOG-Edit 2D) is a GUI based editor and assembly environment for RT Software's OEM render engine, and provides an advanced toolset that facilitates reusability of graphical content for fast graphic creation.

Swift provides the interface that enables designers to author graphical templates, by importing graphics assets produced in industry standard content creation applications, such as Adobe Creative Suite.

Inputs for dynamic content, such as text, bitmap, or video clips are added during the template creation process from within the Swift editor.

The types of graphics that are authored with Swift are typically channel bugs, lower thirds, snipes, tickers and squeezebacks that form branded promotional content for channel networks.

Accessing and Using the Manual

The *Swift* manual is the operator's reference manual that details all the features, functionality and tools accessible in the current version of *Swift*.

Some examples are given where appropriate to clarify use but to see more in-depth, training-related material on creative operational usage, techniques and workflows please refer to the appropriate training materials and tutorials.

The manual is accessible from the RT Software website, available to registered users via login and password:

www.rtsw.co.uk

From within the application itself, links are provided to the above address. The manual is currently in pdf format, and requires the appropriate plugin from Adobe to read. The Swift manual has indexed contents enabling click and go to page functionality.



Command line arguments

There are a number of command line arguments with which you can start Swift to override the default preference settings.

Command Line Argument	Description
help	Show a help message listing available command line arguments
version	Show the current version of Swift and exit
prefs <file></file>	Load the specified preferences file instead of the usual preferences file.
project <file></file>	Load the specified project instead of the project in preferences
customProject <file></file>	Load the specified project instead of the custom project in preferences
noProject	Do not load the project specified in preferences
noCustomProject	Do not load the custom project specified in preferences
cue <port></port>	Set the port for a serial cue device
run <runmode></runmode>	Sets the mode that Swift will run up in, overriding the mode set in preferences. SWIFT must be licensed for the mode specified for this to work. Current available modes are playout , live , edit , and sports
preview	Runs up Swift as a preview renderer
diags <true false=""></true>	Show or hide the diagnostics window in live mode.
remote <mosid> <ncsid> <encoding> <timeout> <upperport> <lowerport></lowerport></upperport></timeout></encoding></ncsid></mosid>	Turn on remote mos control
cache	Enable caching of scripts when running in the remote mos control mode
custom <addr> <port></port></addr>	custom plugin protocol control (use addr=none for server)
render <addr><port></port></addr>	tog->tog client/server (use addr=none for server)



plugin <dir></dir>	Specify a directory to load plugins from
sound <true false=""></true>	Enable sound
qscreen <0/1>	dual Quadro SDI o/p
locale <locale></locale>	Choose a locale
analyser	enable parallel port for logic analyser
dvsCard <#num>	dvs video card number
systemDir <dir></dir>	override the Swift system directory
messagesDirectory <dir></dir>	directory for offline render messages
controlURL <url></url>	control machine for remote scenegraph interaction
layerRouting	Enables layer routing. See the layer node reference for more details.
SDI2	Enables a second set of SDI output channels, if available
mux	Turns on Foreground/background alpha-muxing, compataible with Ultimatte external mixing.
vr <vr_type> <vr_file></vr_file></vr_type>	Allows you to specify the VR tracking type and calibration file from the command line.
videoDisplayRender (true/false)	Turns on or off the monitor render display
punditInterface <punditdir></punditdir>	Specify the name of the pundit .pro file from the command line.
skinDirectory <skindir></skindir>	Specify the tog sports pundit skin directory from the command line.
lws <web_directory> <port></port></web_directory>	Setup the tog web server from the command line.



Project Components

Directory Structure

Swift holds all of the assets and graphics required to run a show in a coherent set of directories called a project. See below.

The Project directory shown to the right is a set of mostly empty sub-directories that are created by Swift in a specific location on the disk. The user will define the name of the Project directory and a project file will automatically be created with the same name, inside the Project directory.

The project is laid out under two directories. GMScript holds the graphic and graphic sequences. GMData holds the graphical elements themselves.

The sub directories and directories are automatically created and named by Swift and should not be renamed under most circumstances.

> Project Directory

- GMScript
 - Templates
 - □ Lib
 - Stacks
 - Save
 - Backups
- GMData
 - CGProgram
 - Extruders
 - □ FBX
 - Fonts
 - Geometry
 - Images
 - LineStyles
 - Maps
 - Materials
 - Paths
 - Plugins
 - Shaders
 - Sounds
 - StaticMaps
 - Textures
 - □ VR



Project Folder

When a new project is created, it will be filled with the folders mentioned above and a file.

퉬 GMData	28/04/2016 16:01	File folder
GMScripts	28/04/2016 16:01	File folder
Docs.prj	28/04/2016 16:01	PRJ File

Project files (.prj)

Project files are created automatically when a new project is made. The project file is placed in the root of the Project folder and is suffixed ".prj". It contains default project information including the project name itself. It can be opened and edited with a standard text editor.

Script and associated files

There are commonly up to 4 files created with each new template which are associated with it.



Script files (.rb)

Script files are created automatically when a new graphic template is saved. The script file itself is more commonly referred to as a graphic or template. The script file is always saved in the GMScripts/Template folder and is suffixed ".rb". It contains default script information including the Swift version. It is a Ruby file and can be opened and edited with a standard text editor.

User Interface files (.ui)

User interface files are created automatically only when a new graphic template that contains an input is saved. The user interface file is saved in the GMScripts/Template folder and is suffixed .ui. It only contains information regarding the properties of the input for generating the graphical user interface.

Asset files (.assets)



Asset files are created automatically when a new graphic template is saved. The asset file is saved in the GMScripts/Template folder and is suffixed .assets. It only contains information regarding imported assets. It can be opened with a standard text editor.

Manifest files (.manifest)

Manifest files are created automatically when a new graphic template is saved. The manifest file is saved in the GMScripts/Template folder and is suffixed .manifest. It only contains information regarding methods and inputs. It can be opened with a standard text editor.



Project menu

Projects in Swift are typically used to contain graphic templates relevant to one particular use or client. For example, if the Playout solution requires the transmission of 8 separate networks, it would be realistic to create 8 projects, each project only containing templates relevant for that network only.

New Project

To create a new project, click on the pull down menu "Project" and select "New" or click the new icon on the project toolbar. This will pop up the New Project dialogue:

✦TOG New Project	? ×
Location	
A	F
Name	
	OK. Cancel

Select a suitable location and name for the project and press OK. A new project subdirectory will be created in the location specified and named appropriately. The subdirectory will also be filled with all the subdirectories Swift needs.

Open

Select Open from the project drop down or toolbar to open an existing project. Navigate to the required project directory and select the associated ".prj" file. Once selected, any open project will be closed and the selected project will load into Swift.

Save

Select Save from the project drop down or toolbar to save the currently open project. The user will be prompted to save the current graphic and modified Shaders.

Save As

Select Save As from the project drop down or toolbar to save the current project to another location. The user is prompted for a new project file name and directory. The project will then be saved to the new directory using the name provided.

Recently Opened

Selecting this from the project drop down will display a list of recently opened projects. Selecting an item from the list will have the same effect as browsing for and opening a project via the Project -> Open menu option.



Close

Selecting Close from the project drop down or toolbar will close the currently opened project. The user will be prompted whether or not to save any changes which have been made to the project.

Project Settings

Selecting Project Settings from the project drop down or toolbar will pop up the Project settings dialogue. This provides the full path name to the project file itself and four general settings under the tabbed headings.

Export Project

Selecting Export Project from the project drop down will open an export project wizard, following this will export your work. It will first prompt to ask if it is ok close the currently open project. After selecting yes, it will then present the choice of exporting as a Folder or a Zip, a project destination, an asset prefix and a regenerate script manifests.

Generate Manifests

Selecting Generate Manifests from the project drop down will close the currently open graphic and generate the ".assets", ".manifest" files for all of the graphics in the project as well as any files for the project ".prj" file itself.

Project Settings

Script Directories

This allows the user to specify locations for the project components located in GMScripts (see: Directory Structure).

Project Settings C:/Users/Justin/Desktop/Test/Test.prj		?</th
Script Directories Data Directories Database Transition Ma	ар	
Scripts		Libs
C:\Users\Justin\Desktop\Test\GMScripts	- 🔁	C:\Users\Justin\Desktop\Test\GMScripts\Lib
Templates		Stacks
C:\Users\Justin\Desktop\Test\GMScripts\Template	- 🔁	C:\Users\Justin\Desktop\Test\GMScripts\Stacks 🗾
Backups		Save
C:\Users\Justin\Desktop\Test\GMScripts\Backups	- 🔁	C:\Users\Justin\Desktop\Test\GMScripts\Save 📂

Scripts

This is the top directory GMScripts, which contains the following:



Templates

These are the main graphics that are run from playout, live or sports

Libraries

These are reusable drop in modules that may be used in templates.

Stacks

This is the location of graphic sequences saved from playout or sports.

Backups

This is the location of auto and manual backups made during edit.

Save

This is not used.

To change the current location, click on the file chooser button, navigate to the new location and press OK.

Script/Method Hot keys

This allows a user to assign up to 3 graphics to the function keys F4, F5 and F6. These are only used in Playout.

Data Directories

The Data Directories tab allows the user to specify locations of project assets located in GMData (see: Directory Structure). The default location is in the project folder, it is possible to change the locations of them, click on the file chooser button, navigate to the new location and press OK.





Data Directory

This is the main GMData folder. It should contain the following directories:

Images

This folder holds all of the images that have been imported into Swift.

Fonts

This folder holds all of the fonts that have been imported into Swift.

Materials

This folder holds all of the materials for the project.

Textures

This folder holds texture information. Textures reference the images in the project and give Swift additional information about how to display them.

Shaders



This folder holds Shaders. Shaders tell Swift what states, textures and materials to look for.

Folders Not in Use for 2D

Many folders in Swift are useful for tOG 3D so that it is possible to open 2D projects in the 3D editor. Though these folders may contain some default files, there will be no need to edit or remove them.



Database

The Database tab allows the user to specify databases for this project. Databases are available as sources on data inputs when building graphics. See the section on Inputs under timeline. Swift has built in support for MySQL, Postgres or any database that provides an ODBC bridge.

Project Settings C:/Users/Justin/Desktop/Test/Test.prj	<u>? ×</u>
Script Directories Data Directories Database Transition Map	
	Database
	Host
	Usemame
	Password
	Driver
	Connection String
	Create Backup on exit
New Delete	Test/Dreate

To create a new database select "New" and fill in the details. Remember to type return after each entry. Once the database is created click Test/Create to test the connection. If the database does not exist then Swift will prompt to create it.

Database

The name of the database. For each database selected in the list appropriate names for Host, Username, Password and Driver are required for input.

Host

Type the Host name in this field. This can be a URL or IP address.

Username

Type the Username in this field.

Password

Type the Password in this field. If there is no password leave this blank.

Driver

Select a driver from the drop down list.

New

Creates a new Database. This will prompt for a database name, then fill out the fields on

Page 22



the right with default information. Click the Test/Create button to apply the changes.

Delete

Deletes selected database from the list.

Transition Map

When running graphics in a live environment, it is a common requirement to have some level of automation over which graphics are on air, and which ones are not.

As a simple example, imagine that you have a Lower Third graphic, and a Full Form graphic. Having both on the screen at once would cause the graphics to overlap, so you want to make sure that both cannot be on screen at the same time.

You could do this manually, by calling the appropriate methods yourself, but this puts the workload onto the operator, who may make mistakes.

Transition Maps allow the logic of how graphics interact to be specified at design time.

NOTE: Changes to the transition map are only saved when Ok is pressed.

Project Settings C:/Users/Justin/Desktop/Test/Test.prj	<u>? ×</u>
Script Directories Data Directories Database Transition Map]
Cue Graphic Preroll	
0	
Groups	
	Graphics
	Pattern
Add Remove	
Belations	
	Trigger Group
	*
	Target Group
	· · · · · · · · · · · · · · · · · · ·
	Action
	None
	Hide Offset Fields
	0
	Show Offset Fields
Add Remove	
	OK Cancel



Groups

The transition map logic works as relationships between groups of graphics.

To add a group, click the Add button. To delete a group, click the Remove button.

A group can be anything that you wish. These would all be valid groups :

- Lower Third Strap
- Bug
- Full Frame Graphic
- Election Map
- Clock
- Stats Graphic

Graphics can be added to **groups**. A graphic can be in as many groups as is required. Taking the example groups as mentioned above, a clock graphic could be in both the **Clock** group, and the **Lower Third Strap** group. Similarly a histogram graphic might be in both the **Stats graphic** and the **Full Frame Graphic** groups.

The **Graphics** list shows a list of all graphics in the project, with graphics in the **currently** selected group appearing selected.

Ctrl+Click to select or deselect new graphics into the currently selected group.

Relations

Relations define actions that occur when a graphic is run in Swift. The type (action) of the relation will occur if :

a graphic is currently on-screen from the source group.

The graphic coming on is from the destination group.

The action will apply to all graphics that currently match these criteria.

The available actions are described in the following table

Action	Description
BringOn	Call the bringOn method of the graphic in the source group
TakeOff	Call the takeOff method of the graphic in the source group
HideShow	Call the hide method of the graphic in the source group when a graphic from the destination group leaves the screen. Once there are no graphics from the destination group on screen again, call the show method.



View Menu

Switch to Playout Mode

This option will switch Swift to the Playout Mode for testing graphics. The Playout Mode is explained in more detail later in this manual.

Edit Menu

The Edit menu contains the controls for Undo/Redo, and the Preferences where configuration for internal parameters and external devices can be accessed.

Undo/Redo

ゥぐ

Undo/Redo is accessible via the Edit menu or via the toolbar. Swift supports undo/redo by saving the complete graphic before any operation that might alter it.

These undo/redo files are saved in the Backups directory of the project. The depth of undo/redo is only limited by disk space. The user can regress and progress through these files using the Undo and Redo tools on this menu.

The hotkey for Undo/Redo is: Ctrl + z

Preferences

There are a range of parameters held within Swift which define its operational environment. Once specified, they do not change. They are accessible through the Preference Dialogue under the Edit menu tab or the Edit toolbar. (You can also access these in Playout).



Protocol tab

The protocol tab allows the setup of devices that control Swift, or that Swift can communicate with.

For more information on controlling Swift remotely, see the tOG Playout manual, and tOG Live manual.

Preferences C:\Users\Justin\AppData\Roaming/RT	Software/tog2dsettings.i	ni	<u>?</u> ×
Protocol Video Audio NDI Locale Annotation Protocol None Mos Render Custom PBAK NO PROTOCOL	s Run Mode Layoff Web Server Web Server Directory C:\Users\tog\Desktop\RT Video Streaming Bitrate (Mir 10000,10000,10000	Text Safe Markings SW Cristant/Max)	Port 5001 🛊
Cue Device Type: None 💌	Default Web Pundit Stream Screen Opta Address UserName Inhow	Password	Port 80 🛊
			M.
		Cancel	Save

The Protocol section sets up a protocol that Swift will recieve commands from.

None

Swift is not being controlled externally. This is the default

MOS

Swift can be controlled by sending MOS messages to it using sockets. This is mainly used for playing graphics and methods. The protocol is described in the Live manual.

Parameter	Description
MosID	The identifier for the Swift system when running in Live mode. Included in all MOS messages sent between the systems.
NcsID	The identifier for the application controlling Swift remotely.



	Included in all MOS messages sent between the systems.
Encoding	The character set encoding of the messages, either unicode (utf8) or ascii.
Timeout	If a message is not received by Swift within this time the client application is disconnected. Usually, the systems should heartbeat each other more regularly than this timeout time.
Lower Port	The client application send commands on a socket connected to this port.
Upper Port	The client application reads status messages from a socket connected to this port.
Cache Scripts	If this is selected Swift will not clear out and destroy graphics after they are no longer needed. SWIFT keeps and reuses them. This speeds up loading.

Render

Render mode in Swift allows the user to connect Swift to other tOGs. For more information, see the tOG Playout documentation.

Custom

The Custom protocol tab allows a 3rd party to attach their own protocol layer. This is

achieved through the use of a shared object - either dso (linux) or dll (windows). This means that you can repurpose existing interfaces to drive Swift. See the Plugin manual for more info.

Parameter	Description
Port Number	The port number for socket connections between the systems.
Address	The server address. This is only required by a client, it is blank for a server.

Web Server

It is possible to communicate and control Swift over standard Web Protocols. For more information, see the **tOG Web Api** manual

Parameters	Description
Web Server Directory	The Web Server Directory defines the root directory for the tOG
	web server. Any files in this directory or it's subdirectories will
	be served up by Swift when requested via a HTTP request (for



	example, from a web browser)
Port	The port determines which port the tog web server listens on.
	Setting the port to 0 disables the web server and the web APIs
Video Streaming	Video streaming will adapt to the network constraints to provide
Bitrate	the best experience possible. The bitrate will start at the Starting
	bitrate (the middle of the three values), and based on the
	performance of the network, the bitrate may grow up to but no
	more than the Maximum value, or shrink to no less than the
	Minimum bitrate. The bitrates are in kilobits/second.
Default Web Pundit	Allows the selection of a default pundit to be used by a web
	page. The web page must be designed to make use of the
	default web pundit, as it can override this settings if it wishes.

Cue Device

Swift graphics can contain cue points which allow sequences and animations to be paused. Cue devices provide a remote means of triggering cue points allowing the graphic to continue with the next animation block. Swift supports 3 device types, GPI, serial and Wii.



GPI

The gpi device consists of either 2 or 16 inputs depending on the device installed (see External Devices in the next section). Select the checkbox to assign which GPI channel triggers the cue

Serial

Parameters	Description
Device	This defines the serial port address, It has the form /dev/ttyS0/1/2 under Linux and com0/1/2 under Windows
Device Baud Rate or Input Number	If the cue device is a serial port address then this will be the baud rate.



Video tab

The Video tab allows a user to specify the video devices in use, formats, size, filtering, keying and more, for broadcast SD/HD video in and out. Note that depending on what you change, you will have to restart Swift for it to take effect (you will be prompted when this is the case).

Preferences C:\Users\Justin\AppData\Roaming/RTSoftware/tog2dsettings.ini								? ×
Protocol Video	Audio	NDI	Locale	Annotations	Run Mode	Layoff	Text Safe Marking	IS
	Card No			Start Channe	el	I/P	Channel Count	
	0					1		
📃 Use AJA	Format		MOTEO74					
	V 100	01 33.34 3	IMIF E 274					
Genlock——				- IPMods		ds	Genlock Timing—	
		<u> </u>	Genlock		n L Ne Ts	, i	O Distance (pixels)	
No Sync detect	ted						VSvnc (Lines)	
							0	
		evel `	Tupe (3G-C]] plu]		Dieplau Sore	en Besolution	
Flicker Filte	er	Leve	4A	, (iiy)		Run Width	Run Height Apsect	
UnShaped	Outout					1920 💂	1080 🗧 1.7778	
Watchdog					E	dit Size %	Playout Size \$	*
						93	50	
<u>-</u>								
							Cancel	Save

Output format

Choose the appropriate video format from the drop-down menu.

Resolution

If a video output is selected, this will determine the Run Width and Height. For all cards except Custom these values are fixed. In custom mode, the user can specify the Run Width and Height and aspect ratio.

Run Width

The width of the output window

Run Height

The height of the output window



Aspect Ratio

The ratio of width to height of the run window

Edit Width

The width of the edit window, within the scene editor window

Edit Height

The height of the edit window, within the scene editor window

Playout Size %

This determines the size of the preview screen in Playout mode as a percentage of the render size. If the user is running HD then this should be set at 50%.



Audio tab

This option will load the OpenAL sound manager when Swift restarts. With this you can play out .wav files or output sound from mpeg streams. Please ensure no other device is using the sound device when you select this option.

Preferences C:\Users\Justin\AppData\Roaming/RTSoftware/tog2dsettings.ini								
Protocol Video Audio	NDI Locale	Annotation	s Run Mo	ode Layoff	Text Safe Mark	lings		
Enable Audio I/O	Master	IN1	IN2 Ma:	🔵 IN3	⊕ IN4 ¢) OUT		
Testing Testing Tone 300 ‡ Hz Interface Reset Faders Toggle Mute All	Input Master 	Input Group 1 	Input Group 2 	Input Group 3 	Input Group 4 	put ster - - - - - - - - - - - - - - - - - - -		
					Cancel	Save		



NDI tab

Preferences C:\Users\Justin\AppData\Roaming/RTSoftware/tog2dsettings.ini								? ×	
Protocol	Video	Audio	NDI	Locale	Annotations	Run Mode	Layoff	Text Safe Markir	igs
NDI Inp Input 1 Input 2 Input 3	uts					NDI Output		,	
Input 4 Input 5 Input 6									
Input 7 Input 8									
								Cancel	Save



Locale tab

The locale allows the user to define some start up options for project launch paths and associated files.

Preferences C:\Users\Justin\AppData\Roaming/RTSoftware/tog2dsettings.ini							
Protocol Video Audio NDI Locale Annotations Run Mode Layof	f Text Safe Marking	gs					
Default Project Default New Project							
Use Current		<u> </u>					
Custom Project Default Graphic		Usa Dunawi					
Current E data	econds)	ove contern					
gvim f							
External Assets Graphic Save Count							
10		•					
Locale Movie Loader Buffer Len	gth						
50							
ErrorLog Directory							
	Cancel	Save					

Default Project

If Swift is loaded up and no project is included in the command arguments, then the project specified here is loaded. If this is blank, then nothing is loaded on startup (unless included in command line arguments).

Default New Project Directory

New projects are created in this directory.

Custom Project

The custom Project option is not applicable to Swift.

Automatic Save Period (seconds)

If this is non-zero, Swift saves the current project, graphic and Shaders periodically at the interval.



Import Directory

This directory is periodically checked for new files to import into the current project.

Graphic Save Count

The maximum number of graphic backups maintained by Swift.

Locale

Specifies the Locale i.e. the geographic location. This is used to determine local differences to time and language.

Annotations tab

This groups together preferences concerned with interaction on the screen.

Snap Grid X Size

The x interval in the snap to grid. The default value is 21.1675.

Snap Grid Y Size

The y interval in the snap to grid. The default value is 32.


Node Copy Offsets X

Offsets the x position on node copy by the specified amount.

Node Copy Offsets Y

Offsets the y position on node copy by the specified amount.



Run Mode tab

Run Mode has 3 options.

Preferences C:\Users	\Justin\AppData\R	oaming/RTSoftware/to	og2dsettings.	ini	<u>? ×</u>
Protocol Video Aud	lio NDI Locale	Annotations Run Mo	de Layoff	Text Safe Markin	gs
Startup Mode					
💿 Edit 🕥 Playout					
Debug Level					
Startup	MOS Protocol	Scenegraph	Socket	🔲 Databa	se
Destructors	Script	🔲 Video 🔰	WebServer	📃 Clip	
Display	Animation	Render Protocol	Select	📃 Image	
Preview Control	UndoRedo	Sync to Mc	nitor	Just-in-Time A	ssets
Enable	🖌 Enable	Enable		🔲 Enable	
Stack Parameters	Loop Playout		Log Timing-		
Enable	Enable		🔲 Enable		
0	4	•	50.0	i i i i i i i i i i i i i i i i i i i	Threshold
Performance					
				Cancel	Save

Undo/Redo

Turns on an off the undo/redo manager. The undo/redo manager. The default is set to on.

Loop Playout

Enables the looping of stacks in Playout for testing purposes.

Stack Parameters

Stack parameters enable the user to define how many inputs become available to testing in Playout. Clicking Enable will mean the value entered will provide this many inputs.



Layoff tab

The layoff tab allows you to choose the file format that will be used when laying off graphics as movies or image sequences to disk.

The settings here are used when :

- Laying off a graphic sequence from the editor. (See page Error! Bookmark not defined.)
- Laying off a graphic sequence from playout. (See the playout manual)
- Recording a tOG Sports stack sequence to disk. (See the tog sports manual)

Preferences C:\Users\Justin\AppData\Roaming/RTSoftware/tog2dsetting	s.ini	<u>? ×</u>
Protocol Video Audio NDI Locale Annotations Run Mode Layoff	Text Safe Marking:	5
Protocol Video Audio NDI Locale Annotations Run Mode Layoff FileName Default Directory G:\SalesVideo\Graphics assets\Clips Image </td <td>Text Safe Marking</td> <td>3</td>	Text Safe Marking	3
DNXHD		
	Cancel	Save

Option	Description
Layoff Filename	The name of the file that will be layed off. The correct file extension will be automatically applied based on the format settings
Layoff Type	Whether you are laying off a movie or an image sequence This affects the format options available.
De Interlace	If checked, the video will not be rendered interlaced, even when the video format of Swift is an interlaced format.
Cue Frames	This specifies how many frames before and after the video will be recorded before the video starts properly.



Movie Layoff Options

Option	Description
Format	The file format that will be saved. For example, .mov, .avi.
Video Codec	The video codec that will be used. The choice is limited by the chosen format.
Audio Codec	The audio codec that will be used. The choice is limited by the chosen format.
Movie Bitrate	The movie bitrate that will be used, if appropriate (not all video codecs support a range of bitrates)
Frames Per Second	The number of frames per second that the movie should be played at.

Image Layoff Options

Option	Description
Separate Alpha	Write the alpha of each image out as a separate file.
Zip Files	Save images into a zip file.
Odd Field Dominance	Frames are interlaced by using the odd field of the first frame with the even frames of the second.

Video Layoff Formats

Format	Available Video Codecs
mpg	MPEG1, MPEG2
avi	MPEG1, MPEG2, MPEG4, MJPEG, FLV, UNCOMPRESSED
	YUV422, UNCOMPRESSED BGR, UNCOMPRESSED BGRA,
	HUFFYUV, HUFFYUV+ALPHA, TARGA,
mov	MJPEG, MPEG2, DNXHD, MPEG4, QTRLE
mxf	DV100, AVC50, AVC100, DNXHD, MPEG2,
dv	DV100, AVC50, AVC100,
flv	FLV
m4v	MPEG4
mp4	MPEG4
wmv	WMV



tmv	TMV
mkv	MPEG2, MPEG4, MJPEG, FLV, HUFFYUV, HUFFYUV+ALPHA



Text Safe Markings

SWIFT displays the text safe area on the screen when in Edit mode. These text safe areas are setup here. Swift has its own values for safe areas for various formats but these areas can vary from geographic area to geographic and from broadcaster to broadcaster.

🔶 Preferences C:\Users\Jı						<u>? ×</u>
Protocol Video Audio Video Format	NDI Locale	Annotations	Run Mode	Layoff	Text Safe Marking	
GM_VID_FMT_1080P_50 Text Safe Markings		-				
Left 3.5	Bottom 3.5					
Right 96.5	Top 96.5					
Picture Safe Markings						
Left 5	Bottom 5					
Right 95	Тор 95					
Restore	Defaults					
					Cancel	Save

Video Format

Selecting an option from this dropdown menu will supply the fields underneath with the correct information for that format.

Text Safe Markings and Picture Safe Markings

These settings can be customized if a video format doesn't match the broadcaster's safe markings.

Restore Defaults

Resets the safe areas to defaults.



Graphic Menu

The Graphic Menu contains all the items related to individual graphics or scripts contained within a project. The graphic options are also accessible via the toolbar pictured below.



New

Create a new graphic and provide a name. This will typically be the first action to do after creating a project.

	? ×
Create	Cancel
	Create

Open

The Open dialog presents a list of graphics in the current project. If an icon has been generated for the graphic it will be displayed, otherwise the Swift generic graphic icon will be displayed.

Double click on the icon or select the icon and click on Load Graphic to open the graphic.

Save

Save the currently open graphic.

Save As

Save the currently open graphic under a new file name.



TOG Graphic Editor	? X
_ Includes	
Clear Add	Remove
Custom Transfer Method Name	
Reorder Object Nodes	
CTOGSports	
Ray Casting	
None	
Required Points	
0	
Auto Repeat _ Enable Player Track	king
Stadium Graphic	
	ок

Edit

Offers various options to the user regarding object node, transfer type and ordering priorities for graphics (scripts).

Includes

The user can manage the ruby modules used by the graphic. Ruby modules extend the functionality of the language.

Custom Transfer Method Name

Not available in Swift.

Reorder Object Nodes

Reorder the object nodes in a graphic after transfer to match the order in the graphic.

tOG Sports

This section is not available in Swift.

Recently Opened

Display a list of recently opened graphics. Selecting an item from the list will have the same effect as browsing for and opening a project via the Graphic -> Open menu option.

Reload

Reload the current graphic from disk. All changes to the graphic will be lost. Changes to assets will be unaffected as they are saved independently from the graphic.



Load last undo



Loads the last undo from disk, this is used in unlikely event of Swift crashing. The user can then restore the graphic to the state before the crash.

Export

Exports a graphics and all the assets used in it to the specified directory.

Directory

The assets and script will be saved to this directory.

Assets

The types of assets to export. If Project is selected, a project file will be created in the export directory which references that directory. This effectively exports the graphics into its own project. This will also cause all assets to be renamed (by prefixing their names with the export directory) making them unique (so this script and its assets can be

imported safely into another

Save only the assets saved by the script

Checking this option will not save assets that are not referenced within the script. Any movie files imported, but not referenced with an input will not be exported.

Save to Directory

Saves to a parent folder with all sub-folders and files



Save to zip

Saves to a single zip file

Prefix

Type a prefix that will append a prefix to every file exported.

Revert

This will revert the current graphic back to the previous save, any changes made will be lost.

Close

Close the currently open graphic.



Tools Menu

The tools menu offers options for the import, clean-up and performance testing.

Import

Import is used to import external assets into Swift. The user selects a list of files using the file chooser. Files can be removed and the list cleared using the scissors and trashcan icons. When images, movies or fonts are imported into Swift, they are copied into the ~GMData/Images directory associated with that project. Import Progress shows overall progress and progress per item.



Fonts

Swift can import true type fonts. When imported the fonts are converted into Swift's internal format, for speed of loading and rendering.

Fonts can be imported as Geometric Text, or Textured Text.

Geometric Text

Geometric text models each character of the text as a 3D model, which produces very smooth antialiased text on output that can be scaled to any size without quality loss. In most cases geometric text is used.

Texture Fonts

Checking the Texture Fonts option, imports each character of a font as a bitmap. A subfolder in the GMData/Fonts directory will appear and contain all the character set for the font as bitmaps. These can be post processed in an image editing application such as Adobe Photoshop if required.

Images

Selecting the Images tab within the Import dialogue will provide further options for the import of images and image sequences.





Importing image files

Swift supports a large number of image types, including .jpg, .gif, .tga, .tif, .png and bmp. The recommended file type for still images is .png files.

- All major image manipulation programs support it.
- Images are defined as 24bit and can have an 8 bit alpha channel
- · Images are saved with lossless compression, so the image remains intact.
- Targa files are also recommended because they carry alpha information which Swift interprets on import.

Note: Importing an image into a project in Swift automatically copies it to the correct part of the project directory structure.

Importing movie files

Swift has support for various video formats. Swift uses FFMPEG in order to read these formats, and supports most of the formats that FFMPEG supports. Check the official FFMPEG website for a full list of video codecs located below.

http://ffmpeg.org/general.html#Video-Codecs

Note:

Please refer to the appropriate Appendix for definitive information on video standards, wrappers, codecs and file formats for use in Swift.

Create TMV

tOG Motion Video files (TMV) are like QuickTime movies, but are native to Swift. TMV files are generated from image sequences, typically a Targa stream. TMV files interpret alpha information from image sequences, and deploy the transparency accordingly upon use. TMV files are ideal for small areas of the screen that contain looping animations.

When you select the Create TMV checkbox, select all the files in the sequence in the import dialogue. In the name field, type the name that you want your TMV file to be called and click the Import button.

Premultiply Alpha

Select this option if you want to premultiply the alpha channel of your images on import.

Importing assets from other Swift Projects

Swift can import files from a different Swift project into the current project. Simply select the items you require and click Import.

Page 47



.geo geometry .sha shader .mat material .sta state .txt texture .fnt fonts

Importing a file from a different project will copy it to the correct place in the project.

Importing ZIP files

If you import a zip file into the import dialog, the entire contents of the zip file will be selected to be imported. This is very useful in combination with the Export option to quickly export a graphic and all its assets from one project and import it into another.

Screen Grab

The Screen Grab tool will save the current frame in the editor graphics window out to disk. A file save dialogue pops up to allow choosing of a file to write the image to. When Save is pressed the image will be saved out.

Generate Icon

The Generate Icon tool, generates a thumbnail image for the graphic based on the preview window at the time the menu item was clicked. This icon will then replace the default icon in the Graphics tab, this is helpful for project management.

Clean Project

The clean project tool analyses your project, and lets you remove unused assets.

Purpose

As a project evolves, you will find that there will be elements that you used early on that you replace with other elements. For example, you may have been through several iterations of strap design, replacing old assets with new ones each time. These old assets may not be used anywhere in your project, but they are still loaded in. This has four undesirable effects:

- 1. Your project takes longer to load on startup by loading unneeded assets.
- 2. You project places a greater strain on system resources than it needs to.
- 3. Your project is physically larger on disk, making it more difficult to transfer from one machine to another.



4. Clutters up the project making it difficult to find the correct assets.

Cleaning Your Project

To access the clean project tool, load the project, and select \clean Project from the Tools menu. See below:



Note: Swift will ask you to save your graphic if you have one open; this is to make sure that any recent changes to the project are available to the clean-up tool.

After analysing your project, the clean-up tool will pop up the following dialog.

contains two lists, with buttons for moving assets between the two lists, allowing you to manually select all the assets you would like to keep, or discard.

Unused Assets

This list contains all of the assets that have been located that the project cleanup script believes are not used in your project.

Keep List

It is possible to move assets from the Unused Assets list into the Keep list in order not to lose them during clean up. This can be helpful if there is an animation, input or user code that switches assets since Swift will not be able to detect this.

To move assets from on list to the other, select the assets (either singly or multiple select), and click on the left/right arrows to move the assets from one list to the other.

Note: You should check the unused asset list before continuing.

Performing the operation

After pressing OK, Swift will ask the user whether to permanently delete the assets in the unused assets list, or back them up. When backing up the assets, Swift will ask for a directory to store them in.

Note: Deleting assets is a permanent operation, and there is no way to recover them. If in doubt, choose the backup option.

Note: When backing up assets, it is good practice to choose a new, empty directory. This will make it easy to move assets back into the project if any removed assets were



required.

The project will now be reloaded automatically to take into account the final list of assets. Note any errors that occur and compare them with any errors that occurred before the clean operation. The list should be the same, or possibly reduced.

Testing your project

After cleaning your project, perform a full test of all graphics to verify that the removed assets have not had any undesired effects. In particular, check graphics that set geometries, shaders or textures using inputs, user code or animators.



Performance Dialog

Timing and Performance

Provides tools for testing and diagnosing performance issues within graphics.



Timing Display

These options change the level of timing detail that is overlaid over the graphics. See the Performance Annotations/HUD section below for more information.

Timing Detail

Off:	Do not display any timing data.
Basic:	Display basic timing information, suitable for measuring the performance of all graphics.
Detailed:	Display comprehensive timing, which contains information that may be necessary to provide RT Software's support.

Timing Scope

The timing scope provides basic timing information on a line graph.

Time Base

Chooses the zoom level of the timing scope.



Performance Annotations/HUD

When you activate the Timing Display performance options, the viewport will be overlaid with debug information, so it is possible to check the performance of the graphic. The Timing Scope enabled and the Time Base set to 2. It's important to remember that the performance you get inside the editor may not be the same as the performance from playout, or other automation tools.





Timing Detail

The list of tasks under "Draw" are stages of the render being completed in milliseconds per frame. The number next to Total is the most important to look at, lower is better. Finding the target milliseconds per frame are calculated by dividing the target framerate by 1000. For example 1000/60frames per second gives 16.67ms.

NOTE: Critical values will be highlighted in cyan and yellow.

Bar graph and Timing Scope

The bar graph displays the usage of both the processor (blue) and the graphics card (yellow). Creators should try to keep the bars as far left as possible for the best performance. The timing scope below the bar graph displays the same information but shows it over a span of time, this can be very helpful while playing through methods to determine where any slowdowns are.

Performance Tests

The performance tests deliberately disable or change the way the scene renders in order to help find performance problems. For more information look at the Performance Troubleshooting Guide.

Note: The performance tests are only active while the dialog stays open. This is intentional as a safeguard from them being left on by accident.



Geometry as Cubes

Render all geometries as cubes. Tests for geometry complexity bottlenecks, such as dense polygonal meshes.

Note: Although Swift can't use complex 3D meshes, geometric fonts could cause slowdowns.



Traverse SceneGraph Only

Do not render anything, but traverse the SceneGraph. Tests for SceneGraph complexity bottlenecks.

Grey Lit Shaders

Render all geometries with the same, lit shader. Tests for shader complexity bottlenecks. If this fixes slowdowns it is possible that they were caused by large textures, a lot of textures or complex shaders such as shaders with animations.

Grey Unlit Shaders

Render all geometries with the same, unlit shader. Tests for shader complexity bottlenecks. If this fixes slowdowns then it is possible that it is caused by lights. There may be too many lights in the scene, or too many lights in close proximity to each other.

No Per Pixel Lighting

Turns off all per pixel lighting and Cg Effects. Tests for pixel shader complexity bottlenecks. This is related to Gray Unlit Shaders but test whether per pixel lighting is the cause. **Note:** Per Pixel Lighting is disabled in Swift since there is no 3D geometry to render.

One Light

Prevents more than one light being active when rendering. Tests for lighting-related bottleneck issues.

Backface On

Turns back face culling on. Tests whether back face culling has a significant effect on performance.

Stop Texture Uploads

Stops dynamic textures from being uploaded to the graphics card. This includes movies and TMVs. Tests to see if there is a texture upload bottleneck.

Small Textures

Replaces all textures with a single small texture. Tests to see if large textures are causing bottleneck issues.

Note: All of the shaders in Swift are unlit, therefore testing performance with the Grey Lit,



Grey Unlit or One Light performance options is unnecessary.

Advanced Shader Editor

Please refer to the section on Advanced Shader Editor

Help Menu

All links: RT Software website and FTP

About: Editor and software versions



Preview Window Interaction

Interaction covers all on-screen manipulation of objects within the 2d space. This section covers:

- · Interaction tools/toolbar icons
- · Selecting objects either on-screen or via the scenegraph
- Interacting with selected objects (Translate, Rotate and Scale)
- · Handling multiple selection and using tools with multiple selections
- Editable nodes

Interaction toolbar



The Interaction toolbar is located above the Preview window:

- (A) Reset camera view (after a zoom)
- (B) Show Crosshairs: This displays a crosshairs and centre screen to assist layout.
- (C) Text and Action Safe: Displays safe areas defined in the preferences.
- (D) Snap to Grid: Snaps the selected objects to the defined grid.
- (E) Background Checker Board: Displays a checker board on the render window.

(F) Show Key. Displays the alpha transparency of the composite as black and white (luminance)

- (G) Show Video: Displays the incoming video connected to the video in.
- (H) Translate: Select this icon to translate objects in the viewport.
- (I) Rotate: Select this icon to rotate objects in the viewport.
- (J) Scale: Select this icon to scale objects in the viewport.
- (K) Edit Text: Select this icon to edit text.
- (L) Clear Selection: Select this icon to clear the bounding box.
- (M) Toggle Text Boxes: Toggles all text max size boxes on.
- (N) Keyframe Mode: Allows the editing of keyframes on screen.
- (O) Check video input (Red=Input error; Green=Input source found and displayed)
- (P) Check video genlock sync (Red=Sync error; Green=Input genlock source found)

Page 56



Selection

Selection of objects is performed by clicking on them with the left mouse button from within one of the camera views. Once an object is selected a red bounding box is rendered around the object to indicate that is has been selected. Multiple selection is performed by holding down the Shift key whilst picking objects in a camera view. A bounding box will be drawn around each selected object to indicate that they are selected.

Multiple Selection

Multiple objects can be selected via the picking interface as well as single objects. When multiple objects are selected, they can still be manipulated using the standard tools. Objects are multiply selected by holding down the shift key. When multiple objects are selected the on-screen interaction tools are always displayed at the location of the first node. This is a useful indicator of which node was the first to be selected.

Object Interaction

On-screen manipulation refers to the process of interacting with objects in the world directly from one of the camera views available in Swift. Interacting with an object is performed by selecting the object on-screen, the type of interaction control used depends upon the current mode of interaction.

Conventions

All interactors conform to certain conventions:

Colours are used to indicate the axis a tool or a part of a tool will operate in:

- Red for the x-axis (horizontal)
- Green for the y-axis (vertical)

All tools have two types of operation:

Free

- All mouse movement is mapped back to the interaction tool.
- Movement can occur in any of the two axes:

Constrained

- Movement is restricted to a single axis
- This mode is activated by selecting the appropriate handle on the on-screen interactor. Constrained motion is performed by holding down the Shift key when

Swift

using a particular interaction tool



Free movement

Dragging an object about using the free translation causes the object to remain under the mouse cursor at all times. The actual translation caused by this moving potentially moves the selected object in two dimensions.

Translation

Translation can be performed either by simply grabbing an object on-screen and dragging it or via the use of the axis handles on the translate tool. Dragging an object will cause it to move exactly where the mouse cursor is on-screen.

Rotation

Rotation in the 2d editor only works on the z axis - the axis that goes "into" the screen.

Scale

As per all other interactors the scale tool allows free scaling and axis constrained scaling. The scaling handles are always displayed at a fixed distance away from the centre of the tool irrespective of the actual scale factor of the transform.

As the scale handles are moved the length of the corresponding axes will update to reflect the change in scale, but upon releasing the mouse button the axes will jump back to their default length. The selected scale will remain applied to the object. This approach is used to make the scale tool usable when dealing with small or large scale factors.

Editing Text

Text can be edited directly on screen. Simply select text edit from the interaction drop down menu then click on any visible Text or double click on text in the graphics window to begin editing.

Text can be selected via the mouse and a cursor will be displayed within the text to indicate where editing will occur.

Note: to easily see where text nodes exist on the graphics window use the toggle text box on the graphics window toolbar.

All the standard editing keys (Arrow Keys, Home, End, Delete and alpha numeric keys) are usable. For example with the text as selected above, pressing Delete will remove the selected characters.



Scenegraph Editor

A Scenegraph is a way of ordering the nodes contained in the scene into a hierarchy where parent nodes affect child nodes.

The Scenegraph is basically a tree (really an n-tree as it can have as many nodes as required), in which some action takes place before proceeding to the children nodes.

Scenegraph Toolbar

💐 📓 層 🎶 肯 🔍

The Scenegraph Toolbar contains 5 options:

Find

2

Click the Find tool to search the Scenegraph for particular nodes.

See below:

Name will display all the nodes in the scenegraph that match the letters typed in so far.

Type sorts the list of nodes by type of node.

🕀 Find Node		<u>1</u>	<u> </u> ×
Name			
Туре			
All			-
Name		Туре	
rootNode		RootNode	
DLL_CAM		CameraNode	
DLL_LGT		LightNode	
test_OBJ		ObjectNode	
Altribute	Relation	Value	
		Close	

Toggle Basic Editor

1

Clicking this icon to toggle between the Basic editor (the default) and the Links editor. See below:

Note: For a full descriptions of Links, refer to the Links section.



Object Node Editor



Click this icon to edit the Object Node

The object node is used to specify the layer order of graphic templates.

When graphic templates are scheduled so that more than one is on-screen at once, Swift enables the use of the Layer feature:

A layer with a higher number than another layer will appear on top of that layer on output. Or example:

If a graphic with layer number 0 is scheduled, any graphic that is scheduled with a higher number will apear "above" that graphic.

Clear Scenegraph

--/

Click this icon to clear the scenegraph.

Move Nodes Up or Down



Click the up and down arrows to move nodes up and down the scenegraph.

Dragging a Node

The user can select a node in the Scenegraph and drag it onto another node. As in the last section, if the node has a circle with cross going through it, then the node cannot be moved to the current location as this will result in an invalid scenegraph. Once the user drops the node back into the Scenegraph a small menu will appear with the following options:

Move the branch:

Moves the node and any child nodes

Link to:

Creates a link between the two nodes (see Node/Basic node)

Copy the attributes:

(only works on some nodes) Copy the dragged nodes attributes to the node the mouse

Page 61



pointer is over.

Cancel:

Cancel the move.

Right Click Context Menu

N	Toggle Display	Ctrl+H
T,	Cut	
i.	Сору	
Ê	Paste	
4	Delete Node (inc. subtre	e)
4	Delete Node (exc. subtre	e)
	Rename	Ctrl+R
Ţ.	Add Input	Ctrl+l
7	Toggle Lock	Ctrl+L
8	Group	Ctrl+G
8	Link	
٢	Duplicate	Ctrl+P
3	Alpha	
*	ClipPlane	

Right clicking on a node in the scenegraph will cause a drop down menu to appear. This menu will also appear if the user right clicks on the screen, see below:Toggle Display

This affects the nodes visibility in the scene.

Cut

The selected node and all of its child nodes will be cut out of the Scenegraph.

Copy

This will take a copy of the selected node and all of its child nodes.

Paste

This will paste the contents of the clip board (anything copied or cut from the scenegraph, and any child nodes it has) into the scenegraph as a child of the currently selected node.

Delete Node [inc.subtree]

This will delete the currently selected node and all of its child nodes.

Delete Node [exc.subtree]

This will delete the currently selected node only.

Rename

Type in the new name for the node and press enter to confirm. The user can enter a substitution command of the form "/<old pattern>/<new pattern>". This command will be applied to the node and all its children e.g. to prepped a sub-tree of nodes with "lower3rd_" use the following command "/^/lower3rd_/" where ^ matches the start of the name.



Add input

Adds an input to the node (see inputs).

Toggle lock

Locks a whole sub tree together so dragging any part of it on the graphics window will cause the entire tree to be dragged as if the top transform node has been selected.

Group

Adds a transform node above the selected node/nodes.

Link

Creates a link between the two nodes (see Node/Basic node).

Duplicate

Adds a duplicate node above the selected node.



Graphic and Asset Tabs

The main graphics templates and project assets are accessible from 4 tabbed menus: Graphics, Images, Fonts and Primitives.

Graphic Tab

Graphics	Images	Fonts	Primitives	
	Test			
Save		_oad		8

Description

- References the GMScripts/Template folder within the project
- Contains all the templates within the project

Save	Saves the current template
Load	Loads another template
lcon view	Displays the templates as two column of icons
List view	Displays the templates as a list

Usage

• Double-clicking on a graphic thumbnail makes the template editable



Images Tab

Graphics	Images	Fonts	Primitives			
blar	tk.	default				
Save		Load				2 2

Description

- References the GMData/Images folder of the project
- · Contains all image assets imported into the project
- Images can be both still and moving clips

Usage

• Click and drag an image to the Preview Window



Fonts Tab

Graphics	Images	Fonts	Primitives	1	
A;	a 📗				
Den	Bult				
Save		Load			88 88

Description

- References the GMData/Fonts folder of the project
- Contains all font assets imported into the project

Usage

• Click and drag a font to the Preview Window



Primitives Tab

Graphics Im	ages Fonts Primi	tives		
Circle	Rectangle	Triangle	AudioNode	Clock
Ticker	Roller	VideoScreen Node		
Save	Load			88 85

Description

Primitives describe the basic objects in Swift

Circle, Rectangle and Triangle Creates corresponding shapes for use in the templates

Usage

- Click and drag any primitive to the Preview Window except the Audio Node
- Click and drag the AudioNode to the Scenegraph



VideoScreenNode

Renders the selected video input channel full screen and screen aligned.

Usage

Add a video screen node to the scenegraph, requires a shader above it. The shader must have lighting disabled and no texture.

Interface

n1_VSCR				
VideoChannel	1			
UseFilter	false	4	1 🔴	
Blend	false	Į.	1 🥥	
Translate	960.000000,540.000000	4	1 🏈	
Rotate	0.000000	4	1 🏈	
Scale	1.000000,1.000000	4	1	
HorizontalAlignment	Center 💌	4	1	
VerticalAlignment	Center 🔽	-	1	
TintColour	1.000000,1.000000,1.000000,1.0	🥱 🖡	1	
Display	true	4		

Video Channel	Selects video in channel on ICE
Use filter	Enables anisotropic filtering
Translate	Translates the video screen node in x or y
Rotate	Rotates the video screen node in z
Scale	Scales the video screen node in x or y
HorizontalAlignment	
Centre	Sets the video screen node pivot point to centre
Left	Sets the video screen node pivot point to Left
Right	Sets the video screen node pivot point to Right
VerticalAlignment	
Centre	Sets the video screen node pivot point to centre
Тор	Sets the video screen node pivot point to Top
Bottom	Sets the video screen node pivot point to Centre
Display	Sets the display to visible or invisible (true or false visibility)
InhibitAnimation	Inhibits animated properties within a duplicate node
InhibitAnimationRecursively objects	Inhibits animated properties within a duplicate node's child



ClearRepeatAnimators

AnimationDelay

Clears repeat animators Sets the delay in fields of animators



Clock Node

The Clock node provides the ability to render several different types of timers on screen. The clock can display the system time (with an offset), the elapsed time since a specified time and countdown clocks.

Usage

The user creates a Clock node above a text node. The clock time is then written into that text on every frame. Step animators can be used to set, start and stop the timer.

Scene Graph
⊨- 🔀 clockPosition
Ê" 😈 clock
^t T clockText

Interface

clock				
Clock				
V Running				
Format (hours:minutes:seconds:millseconds hh:mm:ss:zzz) hh:mm:ss				
Offset Millisecs 0				
Туре Absolute				
Time Start Time 0 \0	Elo			
End Time 0 🚔 0				
Count Down	🔜 Stop At Ta	rget Time		
Strip Msecs	📃 Strip Leadir	ng Zeros		
Events				
Time Per	riod	Method		
Add Remove				



Interaction

Property	Description
Running	Starts and stops the clock
Format	The format of the text the clock node writes into the text node. The
	fullest format possible is hh:mm:ss:zzz (eg. 23:59:59:999). The colons
	can of course be replaced by and character. ap can be used for am/pm
Offset Millisecs	When displaying the system time, this offset can be used to match an
	external clock
Туре	There are three types of clock - see below
Start Time	The time the clock will start at
End Time	The end time for the clock
Countdown	The clock counts down to zero time.
Stop At Target	The countdown clock stops when the zero time is reached and doesn't
Time	count through to the next day.

Clock Types

Clock Type	Description
Absolute	shows the system time
Supplied Time Plus Elapsed Time	shows the clock counting up from supplied time
Supplied Time Minus Elapsed Time	shows the clock counting down from the supplied time to the zero time

Events

An event is a method that is called when a certain time is reached

Property	Description
Time	Time from supplied time at which the first event is triggered
Period	The event is re-triggered at intervals of this period after the first event time
Method	The method that will be called as an action of the event
Add	Add an event
Remove	Remove selected event


Notes and Exceptions

Internally, the system clock is used to keep track of the time and not the counting of fields. This means time does not become incorrect when frames are dropped.



Ticker and Roller Nodes

Provides support for tickers and rolling credits.

Usage

A Ticker in Swift is a continuously moving stream of graphic items. This can be classic tickers moving right to left across the screen. It can also be credit rolls moving up/down the screen. The graphic item can be as complex as the user is prepared to build.

To create a ticker popup the custom browser and drag the required ticker type onto the screen (there are two possible tickers - ticker or roller

Interface

This sets general ticker attributes

tickerPosition	ticker	
ticker		
Edit		
Ticker		
Spacing		
100.000000		
Limits		
0.000000,1920	000000	
Speed		
3.000000		
Direction		
Horizontal		
Animation Trigge	er Eivent	
Never		
Pause For A	nimation	
Pause For D	lata	
Wait Duration		
0		
Number Cycles		
1		
🔲 Reuse Slug:	s	
Notification Typ	e	
None		
🔲 Notify On Sl	ug Remov	al
📃 Notify On Sl	ug Insertio	n .
📃 Notify On Ti	cker Off	
Minimum Slug S	ize	
0.000000		A
Maximum Durati	ion	
0		



Property	Description
Edit	Swaps the ticker between Edit and Live modes. When editing, the slugs are displayed stationary. In live mode, the ticker animates as it would in live mode.
Spacing	The distance between the slugs.
Limits	The limits at which the Ticker node draws two clip planes. The slugs appear through one clip plane and disappear into the other.
Speed	The amount the slugs move in a frame. It can also be negative for left-to-right and bottom-to- top tickers.
Direction	The direction of the ticker to either Horizontal or Vertical.
AnimateOffMethod	If the ticker has a numberCycles greater than zero, there is no way to know from a scripting point-of-view when the ticker has stopped. It is impossible to clean up any graphical items that may frame the ticker. If the user supplies an AnimateOff method, the method is called when the ticker runs out of data.
Animation Trigger Event	Animators on a slug's nodes have a special type Trigger. These animators can be triggered on certain events.
Pause for Animation	Pause until the trigger animation is complete
Pause for Data	When the last slug is fully on, the ticker stops streaming the slugs until more data is available. This is only applicable to tickers with network and interface data types and gives the effect of slugs being pushed onto the ticker.
Wait Duration	The ticker pauses for this number of frames after each slug becomes visible
Number of Cycles	The number times to repeat a batch of ticker data. In a database ticker a batch is the result of the select statement etc
Reuse Slug	Saves away old slugs then they are removed and if any new slug contains the same data it uses the save version.
Notify on Slug Removal	This is only applicable when controlling Swift externally using the MOS protocol. It sends a message back to the client whenever a slug is removed.



Source

The ticker can be automatically driven by different data sources. It is updated on each frame. Existing slugs are moved. If there is room, another slug is created and fed from the specified data source. If a slug drops of the end it is removed.

tickerPosition	ticker	
ticker		
Edit		
Ticker		
Source		
_Widget		
Interface None		
Name		
		<u> </u>
_Database		
Name		
None		
Statement		
SELECT <slu< td=""><td>gName>,<</td><td>contents> FROM</td></slu<>	gName>,<	contents> FROM
Delete Or	n Read	

Widget Interface

The type of the data source - None, Database, MOS Parameter or Widget.

Select a user interface and a widget from it. The Ticker node gets its data from this widget. The widget is usually a LineEdit, one line containing the slug Node name and the next containing the contents. Swift uses QT to create user interfaces and their widgets.

Widget Name

The name for the source

Database

A database is supplied with the installation. Select the database and specify the select statement. This statement should have the form 'SELECT <slugName>,<slugContents> FROM ...'. The contents contains a tilde separated list of values used to update the updateable fields. Swift retrieves the



data from the database when the Ticker node has to create a new slug and the data previously retrieved is exhausted. This provides the data for the next set of slugs.

MOS parameter

The controlling program sends a special UPDATETICKER command to Swift. This is detailed in the section on Remote Control.



Update

_	
ŀ	ickerPosition ticker
tic	:ker
	Edit
Ti	cker
S	purce
U	pdate
	Updateable Nodes
	slug slugTextTEXT

Before specifying the data source, first select what nodes are to be updated. Click on the Update tab. This contains a list of all Shader, Geometry and Text nodes in the slug. Only these nodes can be updated by the data source.Fixed Slugs

tickerPosition	ticker		
ticker			
Edit			
Ticker			
Source			
Update			
Fixed Slugs			
No. J. Marca			 Contants
Node Name			Einerites
siug			Second earrole alug
Add	Rei	move	Clear

The user can specify the slugName and contents directly in a table on the interface. This data is the saved to the graphic. The Ticker node will cycle around the list of slugs indefinitely or until the number of cycles is reached.

Button	Description
Add	Add a new slug
Remove	Removes selected slug
Clear	Clears all the slugs



it

it

Node Editor Tabs

When a node is selected in the scenegraph, an editor specific to that node is displayed beneath the scenegraph.

TRFM Editor TAB

TRFM stands for transform. This editor primarily enables the editing and manipulation of position, scale and rotation of graphical objects.

rectangle1TRFM	rectangle1SHDR	rectangle1DGE0M
rectangle1TRFM		
Translate 510.000000,		0,654.000000 🥱 💭 👝
Rotate	0.000000	
Scale	1.000000,1	
ScalePivotPoint	0.000000,0	
Shear	0.000000	
RotatePivotPoint	true	
Disbiak		
Translate		Translates the object in x or y
Rotate		Rotates the object z
Scale		Scales the object in x or y
ScalePivotPoir	nt	The pivot point from the origin of the transform around which
scales		
Shear		Sets the shear part of the transform
RotatePivotPo	int	The pivot point from the origin of the transform around which
rotates		
Display		Sets the display to visible or invisible (true or false visibility)
InhibitAnimatio	on	Inhibits animated properties within a duplicate node
InhibitAnimatio	onRecursively	Inhibits animated properties within a duplicate node's child objects
ClearRepeatA	nimators	Clears repeat animators
AnimationDela	y	Sets the delay in fields of animators



SHDR Editor TAB

There are two shader editors in Swift. Many of the features and tools are shared between them:

- 1. Shader Tab Editor
- 2. Advanced Shader Editor

The former is accessed automatically when a node in the scenegraph is selected, and can be viewed by selecting the Shader tab.

SHDR stands for shader. This editor primarily enables the editing and manipulation of image, colour and visual properties of an object.

rectangle1TRFM rectang		le1SHDR	rectangle1DGE0M	1		
rectangle1SHDR						5
Shader		default	•			1
Colour		1.000000,1.	.000000,1.000000,1.0) 🎵	۲
MoviePauseOnLoad		false				0
TextureT:0		0.000000,0	.000000)	۲
TextureRZ:0		0.000000)	۲
TextureS:0		1.000000,1.	.000000)	۲
TextureImage:0				9) 🎵	۲
TextureImageFlipped:0				9) 🎵	0
ResetMovie:0		0				۲
StopMovie:0		0				0
StartMovie:0		0				۲
StartSound:0		0				0
StopSound:0		0				٢

Shader	Sets the shader with a drop down menu
Colour	Sets the diffuse colour of an object
MoviePauseOnLoad	Pauses a movie clip when the graphic is called
TextureT	Translates the texture on the DGEOM in x or y - if one is present
TextureRz	Rotates the texture on the DGEOM in x or y - if one is present
TextureS	Scales the texture on the DGEOM in x or y - if one is present
TextureImage	Sets an still image onto the texture
TextureImageFlipped	Sets either a still image or clip onto the texture
ResetMovie	Resets the clip to the first frame
StopMovie	Stops a clip at the frame specfied
StartMovie	Starts a clip at the frame specified
StopSound	Stops a sound at the frame specified
VolumeMaster	Sets ganged volumes for all 16 audio channels



MuteMaster	Sets ganged mutes for all 16 audio channels
TextureCopyFrame	Sets the duration for a tmv sequence
Display	Sets the display to visible or invisible (true or false visibility)
InhibitAnimation	Inhibits animated properties within a duplicate node
InhibitAnimationRecursively	Inhibits animated properties within a duplicate node's child objects
ClearRepeatAnimators	Clears repeat animators
AnimationDelay	Sets the delay in fields of animators



DGEOM Editor TAB

DGEOM stands for dynamic geometry. There are 3 dynamic geometries in Swift: Circle, Rectangle and Triangle. This editor primarily enables the editing and manipulation of geometry-specific parameters including aspect ratio.

rectangle1TRFM rectang	le1SHDR	rectangle1DGE0M	1	
rectangle1DGE0M				
Туре	Rectangle		-] 🥥 🔺
RectangleTXSize	1.000000			
RectangleTYSize	1.000000			
RectangleSize	100.000000	0,100.000000		
RectangleRadius	0.000000			
RectangleDAngle	10.000000			
RectangleDX	0.000000			. 🥥
RectangleDY	0.000000			. 🥥
RectangleXGrid	10			
RectangleYGrid	10			
RectangleSizeToTexture	false			. 🥥
Rectangle Stretch Mode	Size To Te	xture 🗖	· .	
RectangleXDelta	0.000000			. 🥥
Display	true			

Туре	Sets the dynamic geometry to Rectangle, Circle or Triangle
RectangleTXSize	No function
RectangleTYSize	No function
RectangleSize	Sets the size in pixels
RectangleRadius	Sets a radius for rounded corners of rectangles
RectangleSizeToTexture	Sets the rectangle to conform to bitmap size (true or false)
Rectangle Stretch Mode	Sets the rectangle to
	Size to Image
	Letterbox aspect ratio
	Pillarbox aspect ratio
Display	Sets the display to visible or invisible (true or false visibility)
InhibitAnimation	Inhibits animated properties within a duplicate node
InhibitAnimationRecursively	Inhibits animated properties within a duplicate node's child objects
ClearRepeatAnimators	Clears repeat animators
AnimationDelay	Sets the delay in fields of animators

Triangle and circle DGEOM options



Equivalent options for triangles and circles are available in the DGEOM Editor.

Reset values



This button enables the rest of current values defaults

Scale linkage



This button enables the linking of x to y scale values

Add Input



This button column adds an input to be added into the corresponding parameters

Add Animator



This button column adds a default-specific animator to the timeline.



Text Editor Tab

Editing Text

Text can be edited directly on screen once Edit mode has been entered. Simply select text edit from the interaction drop down menu then click on any visible Text or double click on text in the graphics window to begin editing. Text can be selected via the mouse and a cursor will be displayed within the text to indicate where editing will occur.

NOTE: To easily see where text nodes exist on the graphics window use the toggle text box on the graphics window toolbar. All the standard editing keys (Arrow Keys, Home, End, Delete and alpha numeric keys) are usable. For example with the text as selected above, pressing Delete will remove the selected characters.

Text Markup

Markup changes the display of attributes of sections of the content by inserting HTML type tags. As the tag is typed into the editor, it will change its appearance on screen and may even disappear. Its not possible to edit on screen directly. They are usually included in inputs or in parameter lists when tOG is driven remotely.

Attribute	Example	Description		
Shader	<s default="">some content</s>	<s shader="">TEXT</s>		
Font <f swis721_bt_bold="">some content</f>		<f font="">TEXT</f>		
Underline	<u>some content</u>	<u>TEXT</u>		
Strikeout	<so>some content</so>	<so>TEXT</so>		
Extrude	<e>some content</e>	<e>TEXT</e>		
Outline	<o>some content</o>	<o>TEXT</o>		
Kerning	<k 0.1,0,0,0="">some content</k>	<k character,word,line,paragraph="">TEXT</k>		
DropShado w	<ds 0,0,0,0.5,0.1,0.1="">some content</ds>	<ds red,green,blue,alpha,xoffset,yoffset=""> TEXT</ds>		
Translate	<tv 0,1,0="">some content</tv>	<tv x,y,z="">TEXT</tv>		
Scale	<sv 0.1,0.1,1="">some content</sv>	<sv x,y,z="">TEXT</sv>		



Changing Content using Links

You can link the **String** property of a text node to other afields to automatically update the string on the text. This can be useful for generating clocking up text when generating a bar chart, for example. By linking the **String** property to the **Scale** property of the bar, and setting suitable scale and biases in the link, the height of the bar could be displayed.

When you link most properties to **String**, you will get a floating point value with 6 decimal places. For example, 5.251392. This is not very useful. It is common to want to reduce the number of decimal places, and also to add text at the beginning and end of the string.

This can be done using the Format option on the the Advanced tab. For example,

- F %.2f%%
- Converts the previous example output 5.25%

Editing Text on Screen

Double clicking on the text puts the editor into on screen editing mode for editable nodes. Select text and the cursor shows up at the selected character. Move the cursor using the arrow keys. Move to the start of the string using the Home key. Move to the end using the End key. Delete characters using the Backspace key. Type to insert characters. Select and highlight a part of the contents by dragging cursor. Type over the highlighted section or delete it using the Backspace key. Changes on the screen should be matched by changes in the contents widget on the TextNode editor (including cursor position and highlighting).

Click on the text with the right mouse button with the control key held down. This pops up a menu of editors. Choose 'text1' and the TextNode editor appears on the bottom right of the interface.

Interface

This interface handles the content of the Text node.



text1TRFM text1SHDR	text1TEXT				
text1TEXT					
String	text3			٢	
Font	Default	-		۲	
Size	50.000000				
XSize	159.097076				
YSize	49.999996			۲	
HAlignment	Left	-		۲	
VAlignment	Bottom	-		۲	
Alignment	Left	-		۲	
CharacterKerning	0.000000			۲	
WordKerning	0.000000				
LineKerning	0.000000			۲	
ParagraphKerning	0.000000			۲	
Underline	false			۲	
StrikeOut	false			۲	
DropShadow	0.000000,0.000000,0.000000	J.O.C		۲	
DropShadowOffset	0.000000,0.000000				
YScaleFixed	false			۲	
MaxXSize	1920.000000			۲	
MaxYSize	0.000000			۲	
FormatString				۲	
AutoWrapXSize	0.000000			۲	
AutoWrapType	Word			۲	
HDirection	Left To Right	-		۲	
VDirection	Top To Bottom			۲	
UsePango	false			۲	
AnimationType	Character			۲	

Contents	This contains the contents of the Text node in UTF-8 encoding and so supports
	the full range of languages supported by the operating system
Font	This is a complete list of the fonts in the project. This can be set on highlighted spans.



String	Sets the text string
Font	Sets the font from the drop down menu
Size	Sets the size in pixel height of the font (50px default)
XSize	Is the size of the incoming text string in x
Ysize	Is equal to the Size

Alignment

Horizontal Alignment	The horizontal alignment (Left/Centre/Right)
Vertical Alignment	The vertical alignment (Bottom/Centre/Top)
Overall Alignment	Combined with the Horizontal alignment this determines the x position of each line of a block of text. For example, if a Text node is Left aligned, all the lines line up with $x = 0.0$. If the Overall alignment is Centre, the longest line is found and this is used to centre the whole text about its y axis
Character/Word/Line /Paragraph	This changes the spacing between characters, words and lines. Swift fully uses the layout information in any font. These are used to tweak the basic kerning and leading. This can be set on highlighted spans.
Max XSize	This fits the whole string into a certain horizontal extent. If the width of the text exceeds this value the whole text node is scaled so it fits
Max YSize	This fits the whole string into a certain vertical extent. If the height of the text exceeds this value the whole text node is scaled so it fits
Autowrap XSize	Any line of text which is longer than the specified size is split up at the nearest previous space and a newline is inserted.
Autowrap Type	Sets the autowrap type to Word or Letter

Styles

Underline	Underlines the selected text



StrikeOut	Strikes out the selected text
Drop Shadow	Sets the drop shadow for the selected text
Drop Shadow Offset	Sets the drop shadow offset for the selected text



Links Editor Tabs

Links connect node attributes together. A link contains the source and destination nodes and attributes and the mapping between them. A classic use is to link the size and position of a square geometry to a text's position and size. The geometry will the fit the text exactly whatever the contents of the text. This is the only way to fit geometry to a text (short of using user code) where the contents of the text is dynamic (eg. in a ticker).

When a node is created its AFields are set up, these are basically the nodes attributes. They can be linked to attributes of other nodes e.g. a Transform node sets up TranslateX and TranslateY.

Links tabs enable access to linking TRMS, SHDR and DGEOM Afields as required.

rectangle1TRFM		rectang	le1SHDR	rect	angle1DGE	ОМ			
re	rectangle1TRFM								
Li	nks								
		Add		Remove		Co	ру		Clear
		Dst Field		Src 1	lode		Sr	c Field	
	1	None		🔹 Non	е		N	one	P
	Tune								
	Data	Type Conve	rsion						•
	Scale					Bias			
	1.000	1000			÷	0.000000			
	Group	Function							
	Avera	age 🔻							
	Expres	sion							

Option	Description
Dst Field	The destination field of the current node
Src Node	The source node
Src Field	The source field in the source node.

The link is evaluated on every traverse of the scenegraph. A list of the attributes from all the sources is compiled. From this list, the value of the attribute in the destination node is derived. There are two methods for deriving the destination value.



Data Type Conversion

Option	Description
Scale	This is multiplied with the result of the group function
Bias	This is added to the result of the group function
Group Function	The specified function (e.g. Average) is applied to all the source field values
Expression	The specified expression is applied to all the source field values. For example, if there are three sources " $(p1+p2+p3)/3.0$ " is equivalent to the group function Average

The best possible match between source and destination is made based on the data types. For instance, if the source is a float and the destination is a string data type, the float is written into the string contents. The most important case is float-to-float because the source can be scaled and biased.

From\To	String	Float	Int	Bool	Enum
String	Сору	Read from string	Read from string	Read from string	Use Enum maps
Float	write into string	Copy with scale and bias	Convert	NA	NA
Int	write into string	Convert	Сору	Convert	Convert
Bool	write into string	NA	Convert	Сору	NA
Enum	Use Enum Maps	NA	Convert	NA	Сору

Range Mapping

The user specifies a set of ranges of source values and corresponding destination values. If the source value falls within one of the source value ranges, the destination field is assigned the destination value.

See this example



Source Value	Destination Value
-100000.0	
-0.1	GM_VA_Top
0.1	GM_VA_Centre
100000.0	GM_VA_Bottom

This mapping is to link the vertical alignment of a Text node to the y scale of a Transform node (ie. a histogram column with text on top). If the scale is positive then the destination value will be GM_VA_Bottom and the text will sit on top of the column. If the scale falls between -0.1 and 0.0, the destination value will be GM_VA_Centre and the text will straddle the base of the column. If the scale is negative the destination value will be GM_VA_Top and the text will sit just below the column. These values are calculated every frame and the decision where the text sits will dynamically follow the scaling of the column.



Miscellaneous Options

These options are available for all node types.

rectangle1TRFM	rectangle1SHDR	rectangle1DGE0M	
rectangle1TRFM			
Links			
Miscellaneous			
Explicit Script V	ariable		<u> </u>
Unshadowed			
Unreflected			
🔲 Initialise Once			
🔲 View Fustrum C	ulled		
Disable Picking			

Option	Description
Explicit Script Variable	Creates explicit script variables for nodes for which this is set
Unshadowed	These nodes are not included in the shadow map calculation if under a Shadow node
Unreflected	These nodes are not included in the reflected scene if under a Mirror node
Initialise Once	For nodes above object nodes, if this is set the node will only initialised in the first graphic it appears in. It is not initialised in subsequent graphics.
View Frustum Culled	Whether view frustum culling affects the node.
Hide From Render	Do not draw this node while rendering the scene. The node will still be drawn when picking. This is useful when working with touch nodes.
Hide From Picking	Do not draw this node when picking. This is useful when working with touch nodes.



TimeLine Editor tab

The TimeLine Editor in Swift borrows much from editors in standard content creation applications from Adobe, Avid or Autodesk. From this interface, template designers are able to edit the duration and temporal position of components, set the appropriate actions that specify the Method and order the animated components in a layered fashion.

TimeLine	Curves	Inputs	User Co	óe –															—II—				
bringDn				G.	3, 00 17	G Cx C	00	w 💱 🆸	Image: A start and a start and a start a st		👌 🛧 🕹	abi 💷								£		of [][]:[][ł. (
	0n																						
				•																			
K N	۰.) U	1	900	00.00.04	00.00.08	00.00.12	00.00.16	ထဲထဲဆဲ	00.00.24	00:00.29	00:00.32	00.00.36	00.00.40	00.00.44	00.00.48	00.00.52	00.00.56	00.01.00	00:01.04	00:01.08	00:01.12	οœι

Methods

Methods in Swift are the part of the graphic that contains information about animations, their durations, and inputs that is called by the controlling application to play to air. Use the drop-down menu to select the Method you want to create animations in. In Swift there are 2 Methods:

- bringOn
- takeOff

Blocks

There is only 1 Block in Swift and it represented by the green line that is always uppermost in the TimeLine Editor. The green line defines the total duration of the Block, which in Swift is the total duration of the Method, including any delays specified in the Curves Editor.



abi 💠

TimeLine Toolbar

	3. 00 16 9. 6- 9. 6. 10 17 10 10 10 10 10 10 10 10 10 10 10 10 10
Add Method	Creates a new method
Cut Method	Cuts a method ready for pasting
Copy Method	Copies the current method
Paste Method	Pastes the current method
Delete Method	Deletes the current method
Rename Method	Renames the current method
Export Method	Exports the current method
Layoff Method	Lays off to clip or sequence the current method
Add new Block	Add a new block
Split Block	Splits the selected block
Flip:	Flips the animation
Cut:	Cut current selection
Сору:	Copy current selection
Paste:	Pastes the current previous cut / copy
Delete:	Delete current selection
Up arrow:	Moves the current selection up
Down arrow:	Moves the current selection down
Rename:	Renames current selection
Scrub movie clip:	Enables the scrubbing of clips when toggled



Transport Controls



Universally standard Transport Controls are used to play through animations. See below:

In addition to the standard transport controls, the timeline can be "scrubbed" using the cursor. Click and drag in the timebar region at the bottom of the timeline. See below:

0 OO	00.0004	00.00.08	00:00 12	00-00 16	00.00.20	00-00-24	00:00.28	00:00.32	
\geq									
P1 1									-

Field Counter

The Field Counter is a timecode display, and is calibrated to number each separate field.

Note: There are 2 fields to every frame of video.

00:00,{of00:00,{

The first timecode box represents the position of the cursor in the TimeLine.

The second timecode box represents the total duration of the Method.

Zoom

Drag the Zoom Slider left or right to focus the view in large or small time metrics. See below:





Creating Animations

There are two different techniques that you utilise to create animations in Swift. The concept behind animations in Swift is very similar to standard content creation applications such as those from Adobe or Autodesk, using "keyframes" to set values of the properties of objects at certain points on a timeline.

Adding Keyframes

۲

Click once in the Animator Icon column of the property you want to animate. See below:

rectangle1TRFM	rectang	le1SHDR	rectangle1DGE0M			
rectangle1TRFM						
Translate		510.000000),654.000000	6	۲	
Rotate		0.000000		9	۲	
Scale		1.000000,1	.000000	\$ 5	۲	
ScalePivotPoint		0.000000,0	.000000	9	۲	
Shear		0.000000		9	۲	
RotatePivotPoint		0.000000,0	.000000	9	۲	
Display		true				

This will create two keyframes, at a set duration of 50 fields, and become visible in the TimeLine. This component is called an Animator. You can animate virtually all the properties of every object in Swift.

Note: When you add Translate or Scale

keyframes, two Animators appear in the TimeLine corresponding to the x and y values associated with position and size information.

Selecting Animators

To select an Animator, either click on the bar or on the object name in the left hand column. Use the Ctrl key and Shift key respectively to select multiple Animators in the standard Windows way.

Editing Animator Durations

You can edit the durations of Animators in the TimeLine by clicking and dragging the ends of the Animator bar left or right. See below:





Moving Animators in time

You can move an within the timeline Animator, by clicking in the middle of the Animator bar, and dragging left or right. See below:

TimeLine	Curves Inputs User Co	te	
bringOn	•	<u> </u>	00:00, (<mark>of</mark> 01:05,0
🕂 🧱 bringOr			
* / / re	ctangle1TRFM:TranslateY		
- <mark>Ale</mark>	ctangle1TRFM:TranslateX		

Node to scenegraph dragging

You can also create an animation by dragging a node from the scenegraph and dropping it onto the ruler near the start frame, at the bottom of the TimeLine window. This will cause Swift to pop up a dialog. See below:



Note: You can do this with all nodes, but unless you drag a Group, Alpha or Clip Plane node to the ruler, you will only be presented with options to animate properties at the geometry level. For nearly all situations, use the Animator Icons within the respective editors to create your keyframes.

Path:	Select Path type from the drop-down menu
Start:	Animator start value
End:	Animator end value
Length:	Duration in fields



Curves Editor tab

The Curves Editor is the window that is used to edit points on an animator and to change the shape of the curve to change the behaviour of your animation. There are 4 types of curves used in Swift. These are Path, Ramp, Step and Cyclic.

Animators: Path Type

Path Animators are commonly known as Bezier curves and are represented in the TimeLine by a red bar. Path Animators (Bezier curves) are common to many standard content creation applications, and they allow the user to change the shape of a curve. When bezier curves are used, there are always at least two keyframes that form the curve. See below:



Keyframe points

A keyframe (value) point is represented by a yellow dot on the Curves Editor. The keyframe represents a knot or value in the path. The vertical displacement of the point is the value of the curve at that point. The horizontal position of the point is the point in the timeline at which the value occurs.

Selecting a keyframe

To select a keyframe, click the yellow dot. A green bounding box will signify its selection.

Editing the curve

To edit the shape of a bezier curve, select the keyframe and then click and drag its "handle" represented by a red dot at the end of the red line. If a keyframe has both an incoming and outgoing curve there will be two control handles on the knot.

Note: For animating motion, a typical use of bezier curves is to induce an "ease-in" or "ease-out" characteristic to the movement of an object.



Editing keyframes visually

To change the value of a keyframe, select it and drag it to the required position in the Curves Editor.

Editing keyframes manually

To edit Path Animators (Bezier curves) manually, select the keyframe and use the input options below:



Current value: To change the value of a keyframe, use the Curr Value string.

Current Field: To change the field that a keyframe is on, use the Curr Frame string.

Path Name: Is not accessible in Swift

Path Type: Use the menu to select an alternative curve type.

Grid sizes

The two spin boxes on the left of the curve editing canvas control the value and frame ranges.

Max grid size: To change enter a new max size

Min grid size: To change enter a new max size

Animators: Ramp Type

Ramp Animators are represented in the TimeLine by a yellow bar. Ramps are in fact straight linear lines between two points.

Note: Animators that use Ramp curves only contain two keyframes.

Editing keyframes visually

To change the value of a keyframe, select it and drag it to the required position in the Curves Editor.



Editing keyframes manually

Offset 0.000000	4 7	
Curr Field 50 🗣	Curr Value 1020.000000 📄 End Frame Var	

To edit Ramp Animators manually, select the keyframe and use the input options below: Offset: Sets an Offset for the ramp by the specified amount.



Animators: Step Type

Step Animators are represented in the TimeLine by a 1 field blue bar. Step Animators set a single value on a specific frame.

Note: Step Animators only contain one keyframe.

Editing keyframes visually

To change the value of a keyframe, select it and drag it to the required position in the Curves Editor.

Editing keyframes manually

To edit Step Animators manually, select the keyframe and use the input options below:

Value	
820.000000	4
Curr Field	Curr Value
1	820.000000 🚔
Start Frame Var	End Frame Var

Value: The Step animator interface will change depending on the field value selected. If the Field value is a float a point edit control will display, For a boolean a check box will appear, For a string value an edit field will appear and for an integer value a spin box will appear.

Animators: Cyclic Type

Cyclic Animators are represented in the TimeLine by a cyan bar. Cyclic Animators enable a continuous oscillation of animations.

Editing keyframes visually

To change the value of a keyframe, select it and drag it to the required position in the Curves Editor.

Editing keyframes manually

To edit Cyclic Animators manually, use the input options below:

Offset Amplitude Phase 20.000 20.000 0 0	Phase:	At what point in the cycle the animation should start (0-90)
0.000	Amplitude:	The height of the oscillations
Curr Field Curr Value	Offset:	Oscillate from one value to another
Start Frame Var End Frame Var	Decay:	Rate at which the oscillations die off



Cycles: The frequency of oscillation

Invert: Clamp oscillations to positive or negative cycles



Common Properties

All animation types support the following common attributes. See below:



Class

The Class specifies the type of animation curve. Use this drop-down menu to change curve type for your selected animator.

Node

This is the list of nodes in the Scenegraph that can be animated.

Field

For a given node this is a list of all fields in that node that can be animated. Note that the fields are restricted to the animation type specified. For Cycle, Path and Ramp these are always real (floating point) values. Step Animators will include Integers, Booleans and Strings.

Repeat

Specifies if the animation should repeat and how it should repeat:

Repeat - For Ramp and Cyclic. Continues the animation infinitely.

Repeat/Reset - For Ramp, Path, Cycle and Step. This is the same as Repeat except the animation will reset to the beginning when it reaches the end.

Reset - For Ramp, Cycle and Path. The animation will reset to its first frame value at the end.

Link Type

Specifies where the initial value comes from.

Absolute - Use the value calculated from the animation.

Relative - Use the current field value as the start value and recalculate the path from this value. This is useful if the user does not know ahead of time the value the field will be starting from.

Relative Offset - Not used.

Offset - Use the current field value as an offset to the animation.



Delay

This is used for text character and Duplicate node animations where the animator is animating multiple objects.

Field Parameter

Parameter passed to the animator that will affect its operation. At the moment, it is used to determine the end of a clip plane animation based on the extent of the nodes underneath it eg. clip on text even when its length is not known beforehand.



Inputs tab

Inputs are the mechanism through which Swift associates external data with node and animator attributes. The Inputs editor is part of the Timeline editor and is accessed through the input tab.

TimeLine	Curves	Inputs	User Co	de						
bringOn			-	0	S C 🐱 S C C 🐨 💭 🖉 💭 🗚	₽				
🗄 🗮 bring	On				urce	Deta	*		Destination	
-14	rectangle11	RFM:Tran	islateY		MOS Parameter		Input Name	Default Value	Type ScriptValue	
	- rectanole11	BEMillion	Natelo						Dynamic 🗹	
1				l î					Data Type String	
										Expression

Inputs can be added, removed, cut and pasted. Inputs are added to the current block so a destination attribute can have more than one input but they must all be on different blocks.

Inputs happen in two stages. First the source data is retrieved. Second, this data is written to the destination. Any user code specified for the block is run between these two stages. This is why input sources have script variables associated with them. The source data is assigned to this variable in the graphic. The user code can then manipulate this script variable. The results of this manipulation will be then written to the destination.

All destination data will be automatically converted to an appropriate form before it is written. For example, an input on a Text nodes font field will be converted from a string to a pointer to a Swift font.

An input on an animator will change the final value of the animation and cause it to be recalculated. An input can be put on a Step animator. When the Step animator is animated the input is evaluated. This allows inputs to be run at a specific frame not just the start of a block.

Details

This lists all the inputs on the current block. Change the block and the list will change. More than one input can be selected and selected inputs can be deleted, copied and cut.

-Details		
	Input Name	Default Value
1	text1TEXT_String	text1

Option	Description
Input Name	The name of the input. It is recommend the user uses sensible names which describe what the input does. For example, lineWidth, showBarChart, translateX
Default Value	The value to set the input to if none is received.



Source

The user selects the source type for the input. There are nine types of input sources.

Source Type	Description
Widget	The source is a widget in a user interface supplied with the graphic.
MOS	The source is from a name/value pair sent to the method by some
Parameter	external means, for example a MOS connection.
Database	The source is a database query
Script Variable	The source is an existing script variable inside of Swift.
Constant	The source is a constant value
SceneGraph	The source is the current value associated with part of the scenegraph.
Touch	The source is a touch parameter when this method has been triggered by
Parameter	a touch event.
TOG Sports	The source is data generated in TOGSports.
Command	The source is the output of a command run externally to Swift.

Widget



The interface widgets come from user interfaces. A user interface is associated with a graphic in the Graphic editor. The user interfaces for a project are stored in the Template graphics directory. The interface can be laid out in Qt Designer externally to Swift and then imported. Alternatively, Qt Designer can be run up for the graphic chooser. When the interface is saved, it is saved automatically to the Templates directory. Swift can also automatically generate interfaces if required.

When Swift is in Playout mode and a graphic is selected, if it has an associated user interface, this is popped up under the stack (if display in stack is set to true). The user enters values and stacks the graphic. These values will be the sources for Interface Widget inputs.

Almost any widget can be used. If a list is used, normally its contents would be retrieved as a string. If its position is required just end its name in '_ascii_'. It is worthwhile naming the widgets in a consistent manner eg. for a QComboBox of fonts for a Text node called title, titleFontCB would



be useful.

Display in Stack

If this is set then this parameter will be listed with the method when it is stacked in Playout mode.



MOS Parameter



The MOS Parameter source type allows access to any name/value pairs of data that have been made available to the method.

The xml MOS messages received by Swift as part of the Remote protocol will contain parameters as name/value pairs. Swift will use the name of this input to retrieve the value for this name from the list of name value pairs. This value it then written to the destination.

It is also possible to add your own parameters in user code, which is useful when calling methods from within other methods.

Filter

Only used when generating interfaces. This allows customisation of the widget created from an input.

If the input updates a font/shader/geometry/texture then the contents of this is used as a regular expression to limit the items in the combo box widget normally produced for these types of inputs (e.g. a texture image being updated and the filter is

/home/tog/*.tga - this filter will cause the file chooser widget generated to default to the directory /home/tog and the file chooser filter will be set to .tga files).

Otherwise this can be used to override the default creation of a line edit and replace this with a combo box. The filter would then contain the location of a file used to set the contents of the combo box (e.g. a text string being updated. Normally a line edit would be generated and the value entered into this would update the text string. If filter is specified to be a file which contains on different lines Left Right, a combo box would be generated with Left and Right as the two choices). When one of these is selected the value will be added to the text string.

Display in Stack

If this is set then this parameter will be listed with the method when it is stacked in Playout mode.

Database


The database source allows you to query a database, and use the result of the query as the data for the input.

Databases are set up via the Project Settings dialog.

There are two forms of the database source editor. A full SQL select statement can be entered into one (allowing all the power and flexibility of SQL data selection). The other is simpler and builds an SQL statement up from its component sections. This makes it easier for an SQL novice.

Source —	
Type Databa	ase
Database	Edit SQL
Table	<u> </u>
Where	
Details	Column 🚬
Eval	

At the moment, the input source is evaluated ie. when its associated block is run, the database is accessed and the statement run on it.

Edit SQL

The user can move between the two interfaces and the statement (or as much has been entered) will be transferred.

NOTE: Complex statements cannot be handled by the simple SQL editor. In this situation, Swift will stay in the full SQL editor to avoid corrupting the SQL statement.

Database

The database of the source - from the project database list

Table

A list of the tables in the database. Only one can be selected. To do table joins use the complete statement entry interface

Where

Insert the where clause here (minus the WHERE)



Column

A list of the columns in the selected table. If selected the column is added to the Details widget

Details

This determines what columns (and manipulation of those columns) are retrieved.

Eval

This evaluates the statement and puts the result into the combo box.

Database Statement

When using the "full" mode, The complete SQL statement is shown here.

Variable Interpolation

You can use variable interpolation to include global variables and the results from other inputs in database SQL queries.

Script Variable



This source type allows access to a ruby script variable that has been previously set up in the graphic. For example, a script variable that was the output of a previous input can be piped into another input.

Constant

Sourc	e	
Туре	Constant	

This value is read in from the default value specified in the input details table.



Scenegraph

-Source	
Type SceneGraph	_
Node Name	
None	V
AField Name	
None	V

The scenegraph source allows a value from a node in the scenegraph to be used as an input source.

NodeName Chooses the node that the value will come from.

AFieldName Chooses the property on the node that the value will be read from.

Touch Parameter and Tog Sports

Are not supported in Swift

Command

Allows an external command to be run. The standard output from the external command will be used as the source value for the input.

For example, C:/Windows/System32/whoami.exe will return the name of the computer that Swift is running on.

You can pass command line parameters to the command you are running by including them like you would normally in a batch script.

You can also use variable interpolation (described below) to allow the values from ruby global variables, and from other inputs in Swift to be used as part of the command line.

NOTE: Commands do not run inside of the editor. Instead, the default value will always be returned. To see the output of your command, run in Live, Playout or Sports modes.

WARNING: Swift will pause execution of the script until the external command returns. The Command source type should only be used with commands that return quickly. If you run a command that does not exit, Swift will become unresponsive.

Variable Interpolation

You can use variable interpolation to include global variables and the results from other inputs on the command line.



Variable Interpolation on Database and Command Inputs

A powerful feature of Swift is that you can modify the Database Input sql queries, and the Command input command line using existing parameters in the system. This can be done for global variables and for MOS parameters.

In order to do this, use square brackets in part of your statement. For example :

• SELECT name FROM addressbook WHERE address = '[\$currentAddress]'

Here, \$currentAddress is a Ruby global variable that we would have previously set up with an address via user code. Note that in order for this to be a correct sql statement, we still need to quote the result with " outside of the square brackets.

Alternatively, the value that we use might be passed to the method. To access the method data, specify the parameter name directly.

SELECT name FROM addressbook WHERE address = '[currentAddress]'

Here, currentAddress would have been set up externally via e.g. mos, another method, a touch event, etc. Method data is populated when an input is evaluated, so any input from a previous block in the same method can be used in a database query.

• Method data can also be populated using the Method Data output type.

Finally, method data can be set in user code as follows :

data.setInputValue(<blockName>, <inputName>, <value>)

Default values for interpolation

When running in the editor, quite often there is no data available. You can choose a default value by adding :<defaultValue> to the square brackets, as follows :

SELECT name FROM addressbook WHERE address = '[currentAddress:12 Chesney Street]'

Destination



All input destinations share the two combo boxes below.



Dynamic

A dynamic input will be evaluated every time the input is run. In most situations, this should be checked.

If an input is not dynamic, it will only be evaluated at the start of the method, the first time that method is run. This can be useful if you are using dynamic data sources, and want to be sure that they don't change halfway through a graphic.

Data Type

This sets the datatype (string, float, int etc) of the source. If the source is going to be manipulated in user code, it is sometimes useful to set the datatype of the script variable

There are five types of input destinations

Destination Type	Description
ScriptValue	The data is stored in a script value, nothing else happens
SceneGraph	The data is pushed to an animatable property (AField) on a node.
Animator	The data is used as the end value of an animator
MethodData	The data is parsed as a list of name/value pairs and used to create new data that can be used in future blocks. The data can be accessed using the MOS Parameter input type.
TOGSports	The data is used to run one of a number of TOG Sports specific actions.

Scenegraph

The evaluated source of the input will be converted and written to this field when the block is run.

-Destinatior	n	
Туре	SceneGraph	
Dynamic	v	
Data Type	Float	-
	Expression	
		_
Node Na	me	
Node Na rectangle	ime le1TRFM	
Node Na rectangli Field Nan	ime leTTRFM ne	
Node Na rectangl Field Nan Translate	ime le1TRFM me le¥	

Node Name

The destination node in the scenegraph



Field Name

The field on the node selected above

Script Value

This creates a ruby script variable and assigns the source to it.

-Destinatior	1
Туре	ScriptValue
Dynamic	v
Data Type	Float 💌
	Expression



Animation

This lists the animators on the current block as <node_name>.<field_name>. The evaluated source of the input will be written to the final value of the animator when it is added to the node. For a Path animator, this will cause the path to be recalculated.

-Destination	n	
Туре	Animation	3
Dynamic		
Data Type	Float	3
	Expression	
Animator	Node Name	
rectang	le1TRFM:TranslateY	

Animator Node Name

This contains the node:field value

NOTE: If the target node is part of a Duplicate nodes prototype node, the results of the source evaluation will be a list and will be distributed among the duplicates. If the source is a database, the list will be the results of the SQL statement. If the source is a constant value, the source will be divided in to a list of strings using '~' as a separator. MOS Parameter and Interface Widget sources are handled similarly.

Method Data

The method data destination type allows the data from the input to be parsed and converted into data paramters that can then be used by the **MOS** input source type in future inputs.

For example, a common situation is where I want to run a database query that returns a table of data. I want each column of data to populate a different node in the scenegraph.

Name	Age	Address
Joe Bloggs	22	3 Kipling Yard
John Doe	42	17 Bloomsbury Avenue

Normally this would be achieved using three inputs :

Source Query	Dest node->afield	
SELECT Name FROM table;	nameTEXT->String	
SELECT Age FROM table;	ageTEXT->String	
SELECT Address FROM table;	addressTEXT->String	



However, if the query takes a long time to run, running the query 3 times can be undesirable. It would be better if we could run the query as follows :

• SELECT Name, Age, Address FROM table;

However, in this case, the data would be interleaved and we would not be able to directly output it into our destination nodes.

Method data solves this by allowing us to form our query so that Method data will split the data up.



MethodData Format

The Method Data destination type expects the input to be in the following format :

• <param1>=<value1>;;<param2>=<value2>;;<param3>=<value3>;;...etc

Each parameter definition should contain the name of the parameter to be set, followed by an equal sign, followed by the value, followed by two semi colons.

If you pass multiple parameters of the same name in the input, they will be collated together and formed into an array. For example :

param1=1;;param1=2;;param1=3;;

will end up with the input param1 containing the values 1~2~3

It is also acceptable to pass arrays of parameter updates to the method data input. For example:

• param1=1~param1=2~param1=3 has the same affect as using semicolons.

Returning to our example, the database query can be turned into a single query that follows the convention expected by method data by using CONCAT to construct the string.

• SELECT CONCAT('name=',Name,';;age=',Age,';;address=',Address,';;') FROM table;

We can feed this to a method data destination, and then use mos parameters to pull out the parsed information, stored in name, age and address.

Source	Dest node->afield
SELECT	METHODDATA Destination
CONCAT('name=',Name,';;age=',Age,';;address=',Addre	
ss,';;') FROM table;	
name (MOS parameter)	nameTEXT->String
age (MOS parameter)	ageTEXT->String
address (MOS parameter)	addressTEXT->String

The method data is most useful when used with the database query source type, as above, and for the command source type, if you write an external command that understands the format expected by Swift.

TOG Sports

This destination type is unsupported



User Code tab

This page allows to user to enter the user code for the current block. The use code block can be made blocking by selecting the toolbar option.

All of a Swift scene is scriptable. Although a suitably large portion of the scripting potential is exposed via Swift's editor interface, there are still times when the user will want to achieve something that is not directly possible. For these situations, the user can use user code.

User code allows the user to add their own ruby scripting code at strategic locations in the Swift script in order to achieve the desired result.

User code differs from editing the script manually by hand, as it is marked up by the editor so that it knows that it is user code and will load/save it correctly.

See the <scripting> documentation for a thorough examination of scripting code. User code is block based - each animation block has it's own User Code Block.

• User code is written using ruby.

Default user code

Default user code is generated for every Swift authored graphic for both default methods:

bringOn

@Test_OBJ.setTransferType(Gm::GM_ONT_Persistant)

takeOff

@Test_OBJ.setTransferType(Gm::GM_ONT_Default)

Changing Input Results using User Code

Quite often, it is useful to be able to take an input and modify it's value before applying it to the Scenegraph. Take a simple example. The input provides a true/false value (either via a checkbox in the interface, or via a database entry). The user wants an object to turn red if the answer is true, and blue if the answer is false. How is this achieved? One answer is to write some user code in order to perform the logic.

Whenever the user creates an input, destination variable name must be chosen. This becomes a variable in Ruby, that can then manipulated using user code.

Let's take the example given above, and see how this works.

We have the following inputs to control the material colour from a database query SELECT isTrue FROM myTable



Src	Src Query	Dst Node	Dst Field	Dst Variable
RedInput	SELECT isTrue FROM	shaderNode	MaterialDiffuse	redColour
GreenInp	SELECT isTrue FROM	shaderNode	MaterialDiffuse	greenColour
BlueInput	SELECT isTrue FROM	shaderNode	MaterialDiffuse	blueColour

We have one input per material colour element. In this case, we want the red green and blue components to be controlled by the same value from the database, but each could be controlled by a separate value.

A true/false query coming into Swift will give us the value of 1 for true, and 0 for false. So, in the above case, if isTrue is true, our material will be set to the colour 1,1,1 (white), and if it is false, will be set to 0,0,0 (black).

Note: Refer to the chapter on user APIs for more information on user code in the tOG 3d Edit manual



Advanced Shader Editor

The advanced shader editor has many options for creating desired materials. Swift has been limited in the Advanced Shader Editor to use only one texture since 2D graphics don't require expensive surface shading. Other 3D related settings will either be disabled or have no effect on the shader. The Advanced Shader Editor will allow for controlling texture animations, panning, tinting, blend alphas and more.

Shader, material, texture and state editing are all done from a single window with a tabbed interface to choose which item is being edited. There is a common control bar used to choose which item is being edited as well as controls for the saving and loading of items: The contents of the drop down list will alter depending upon which tab (Shader, Material, Texture or State) is currently selected and will contain a list of all of the items of the current type.

A shader consists of a material, a state and textures. A single shader can be referenced by any number of shader nodes in a graphic.

NOTE: A change to a shader will affect any objects that have a shader node that references the shader. If in doubt create a new shader.

Usage

Use the Tools Menus and select Advanced Shader Editor. This editor then occupies the Node Editor Tab area at the bottom right of the interface.

Saving changes

Changes to shaders, materials, textures and states are not automatically saved. Changes are remembered in the editor, but the Save button (see below) must be used to make the changes permanent.



When saving state, material and textures the dialog will prompt whether the user wants to save just that item or all changed items. See below:



Choosing the Save All option will save all changes to all items of that category (state, material or texture) that have changed. Saving a shader also saves its material, state and texture.



Advanced Shader tab

The Shader tab contains all the settings associated with assigning its 3 sub-components. See below:

- 1. Material
- 2. State
- 3. Texture

Note: Only 1 texture can be applied in the 2d editor: Texture0

text Image: Shader Shader Material Shader Material text Itext Itexture 0 None Itexture 1 None Itexture 2 None Itexture 3 None Itexture 3 None Itexture 3	text1TRFM	text1SI	HDR tex	t1TEXT]	
Shader Material Material text State text Texture 0 None Texture 1 None Texture 2 None Texture 3 None Texture 3 None Texture 3	text					
Shader Material text State text Texture 0 None Resture 1 None Resture 2 None Resture 3 None Resture 3 None Resture 2 None Resture 3 None Resture 3 None Resture 2 None Resture 3 None Non	Shader	Material	Texture	State	1	
Material text State text Texture 0 None Texture 1 None Texture 2 None Texture 3 None	Shader					
text	Material					
State text Texture 0 None Texture 1 None Texture 2 None Texture 3 None Texture 3 None Texture 3 None Texture 3 None Texture 3	text					- 🍫 🦻
text	State					
Texture 0 None Texture 1 None Texture 2 None Texture 3 None Texture 3 None	text					- 🐺 🎫
None	Texture 0					
Texture 1 None Texture 2 None Texture 3 None	None					- 📲 🗗
None	Texture 1					
Texture 2 None Texture 3 None None None	None					- 📲 🎝
None 💽 🛃 👽 Texture 3 None 💽 💽	Texture 2					
Texture 3 None	None					- 📲 🎝
None 🗾 🛃 🍡	Texture 3					
	None					- 🐳 🎝

Advanced Material Tab

The Material tab contains all the properties associated with the material only. See below:

text1TRFM text1	SHDR te	xt1TEXT		
text				- 💾 🎼
Shader Material	Texture	State		
Material				
Diffuse				
1.000000,1.000000),1.000000			÷
Opacity				
1.000000				<u> </u>
Ambient				
0.000000,0.000000),0.000000			2
Specular				
0.000000,0.000000),0.000000			2
Emission				
0.000000,0.000000),0.000000			2
Shininess			 	
1				
Side			 	
Front And Back				

Note: A Material can be shared by more than one Shader.



Diffuse

Specifies the diffuse material colour used for lighting. The Diffuse colour is perceived as the colour of the object itself. It is the colour that the object reveals under pure white light. Type in RGB values or use the colour wheel icon to select a colour.

Opacity

Specify an explicit alpha value for an object via it's material. Controls the degree of transparency of an object. Type in a normalised value, where 1 is fully opaque and 0 is totally transparent.

Ambient

Specifies the ambient material colour used for lighting. Ambient light is generalized lighting not attributable to the direct rays from a specific light source. Without ambient light, objects in shadow would be completely black. Type in RGB values or use the colour wheel icon to select a colour.

Specular

Specifies the specular material colour used for lighting. Specular colour is what we most commonly think of as a highlight. The colour of a specular highlight is typically the colour of the light source itself. The highlight size is controlled in turn by the "Shininess" value. Type in RGB values or use the colour wheel icon to select a colour.

Emission

Specifies the emission material colour used for lighting. Emission works exactly like Ambient colour, and can be thought of as "self illumination". Type in RGB values or use the colour wheel icon to select a colour.

Shininess

Specifies the specular exponent of the surface. The Shininess controls the spread of specular highlight. Enter a higher value to achieve small, tight highlights. Enter a lower value to achieve a very shiny, burned out highlight.

Side

Specifies whether this material is set for the front, back or front and back of the object.



Advanced Texture Tab

The Texture tab contains all the properties associated with the material only. This page contains all the controls for setting up a shaders texturing. It handles just one texture at a time. The texture tab has 8 sub menus, each relevant to a particular aspect of how to manipulate and apply bitmapped images and video sources to the surfaces of objects. See below:

GlowCircle	eThin					
Shader	Material	Texture	State			
Texture Im	Texture Image					
_Image Sc	ource ——			_ _		
Image				Stereo Source		
GlowCirc	cleThin.png			_		
Cube Ma	p Images —					
Right		🙂 To	р	🥥 Front		
Oleft		🔅 😐 Br	ttom	Back		
Position						
Filter						
Mapping						
Format						
Animation						
Sprites						
Audio con	trols					

Texture Image sub-menu

Select this checkbox and use the browser to locate an image or video file saved on disc, normally in the projects /GMData/Images directory.

Video I/P1 through I/P4

Select this checkbox for assigning incoming live video source other than the main squeezed source. Checking this box will cause the video data to be fed into the texture.

Cube Map Images

Cube maps are not supported in Swift

Blending

The Blending modes supported in Swift are:

Modulate	Multiply texture colour with material colour
Decal	Mixes texture colour with material colour using texture colour alpha
Blend	Blend texture colour with blend colour
	Blend Colour uses the colour wheel icon to select a blend colour

Swift

Page 122



Replace Replaces material colour with texture colour

Add Adds texture colour and material colour



Position sub-menu

Position is used to apply a transformation to the texture coordinates prior to applying the texture to the model - this moves, rotates and scales the texture on the object surface. See below:

text1TRFM text1SHDF	R text1TEXT	
default		v 💾 🎼
Shader Material Te	exture State	
Texture Image		
Image Source		A
Image 💌		Stereo Source
default.png		
Cube Map Images		
🛛 Right	Ο) Τορ	O Front
🗩 Left	Bottom	O Back
Blending		
🗸 Enable		
Blending Mode		
Modulate		
Blend Colour		
Position		
Filter		
Mapping		
Format		
Animation		
Sprites		
Audio controls		

Camera: Specifies a camera perspective transformation to apply to the texture coordinates. The four values are in order field-of-view, aspect ratio, near clip plane and far clip plane. This is used for projective texture e.g. the texture is like the film in a cinema projector which is projected onto the screen and audience.

Translate: Specifies a translation to the texture coordinates.

Rotate: Specifies a rotation to the texture coordinates (specified as x, y, z angles).

Scale: Specifies a scale factor to the texture coordinates.

Note: Swift only supports transforms and scales on the x and y axis, and the z axis on rotations only.

Filter sub-menu

Filtering controls the appearance of the texture image when it is rendered smaller or larger than its original size. There is a performance versus quality trade off with different filtering options. The filter settings are:



Minification

The texture minification function is used when the texture must be shrunk in size. For example if the user has a 100 pixel texture that needs to be applied to a 10 pixel wide geometry, set the minification process to one of the settings below:

- Nearest
- Linear
- Nearest MipMap Nearest
- Linear MipMap Nearest
- Nearest MipMap Linear
- Linear MipMap Linear

Swift



Magnification

The texture magnification function is used when the texture must be enlarged in size. For example if the user has a 10 pixel texture that needs to be applied to a 100 pixel wide geometry, set the magnification process to either Nearest or Linear.

Flicker Enable: Accepts a number between 0 and 16 and controls the level of Anisotropic filtering. The cost of this becomes more expensive the higher the level of flicker filtering applied. Click the checkbox and enter a value (default 2).

LOD (level of detail): Specifies the range of level of details to use for MipMap selection. Enter minimum and maximum level of detail (default 0, 99).

Level: Specifies which MipMap levels texture data is available for/generated for. Enter Base level and Max Level values (default 0, 99)

Mapping sub-menu

Mapping is not supported in Swift

Format sub-menu

The page sets the format of the texture as a whole (e.g. 1D, 2D etc.) and the format of each pixel (e.g. RGBA etc.). See below:

text1TRFM text1SHDR text1TEXT
default 🔽 📔 🖏
Shader Material Texture State
Texture Image
Position
Filter
Mapping
Format
Format Target Texture 2d
Internal Format
Rgb
Wrapping S Wrap Repeat • R Wrap Repeat • T Wrap Repeat •
Animation
Sprites
Audio controls



Target:

Target 1D specifies that the image is a row of pixels. Target 2D specifies that the image is a grid of pixels. The image dimensions should be powers of 2 otherwise the graphics card will use time to scale the image.

Texture Cube Map:

Specifies that six 2D images are required and that they surround the textured objects as the sides of a cube e.g. sky boxes. The images should all be the same size.

Texture 3D:

Specifies that the image is a 3D grid of pixels.

Texture Rectangle:

Specifies that the image is a grid of pixels. The image dimensions need not be powers of 2.



Internal Format:

Most of the items in this drop down have numbers to correlate with their colour bit information. They have been omitted from this documentation.

Alpha 4/8/12/16	- Read the image as an alpha.
Luminance 4/8/12/16	- Read the image as luminance (Brightness).
Luminance Alpha	- Read the image as luminance + alpha.
Luminance32f Arb	- Read the image as 32bit luminance.
Intensity 4/8/12/16	- Read the image as intensity.
R3 G3 B2	- Read the image as RGB332.
RGB 4/8/12/16	- Read the image as RGB.
RGBA 4/8/12/16	- Read the image as RGB with Alpha.

RGBA is default and will suffice for most images, if the image lacks alpha then there may be some performance gain changing the format to RGB, likewise if there is no colour there may be some performance gain switching to Luminance.

Wrapping

Controls whether the texture will tile on the surface it is applied to.

"Repeat" will tile the texture, "Clamp" will disable the tiling and "Clamp to Edge" will repeat the texture's edge.

S = Horizontal

R = Depth, (Not used in Swift)

T = Vertical tiling.

Note: When not working with tiled textures setting the texture to "Clamp" may not improve performance.

Animation

This section allows the user to alter tOG Motion Video/TMV playback in Swift.

Bounce

When this is enabled, the TMV will rewind itself when it reaches the end of its loop.

Frame Delay:



Number of frames to delay the video's playback by. For example, if the video is 25 frames per second, using a frame delay of 25 will play back the video at 1 frame per second.

Number Loops:

The number of loops the video will play before stopping. Setting this number to 0 will play the video infinitely.

Information:

This box contains some information about the video that is loaded.

Number of Frames: This is only available for TMVs, it will display the number of frames in the TMV.

Dimensions: How large the video is in pixels, width then height.

Reset Image:

Resets the video before playing, best left enabled.

Note: Reset Image needs to be enabled in order to use the Pause on Load checkbox under the "Miscellaneous" section.

Sprites

This menu allows the user to control the sprites texture coordinates. This is not useful for Swift.

Wrapping:

Texture wrapping controls how the texture data is referenced when texture coordinates are outside the standard range of 0...1. For a repeating pattern the mode would be set to repeat, but if only a single copy of the texture image should be displayed the mode would be set to clamp.

Repeat:

Causes the texture to be repeated i.e. the texture point referenced by the coordinates 1.5 is the same as the texture point referenced by 0.5.

Clamp:

Causes the texture to not be repeated. When texture coordinates outside the range 0...1 are encountered the values are simply clamped to the range 0...1. This results in the colour value from the edge of the texture being used at any locations where texture coordinates are outside the 0...1 range.



Clamp To Edge:

Very similar to clamp, but ensures that the colour value that is repeated is the exact value that occurs at the edge of the texture rather than an interpolated colour.

Animation sub-menu

This page sets the parameters for animated textures (for textures with a movie file as an image source as opposed to a single image).

Frame Delay: Specifies the number of frames to delay the animation by.

Number Loops: Controls the number of times the animation is looped.

Bounce: Controls how the animation loops. If bounce is enabled, once the end of the animation is reached the animation will play backwards from the end back to the start rather than jumpingstraight from the end back to the start.

Sprites sub-menu

This page sets up the generation of texture coordinates for point sprites.



Audio sub-menu

Sound Enable: ync Audio Frame: Enables sound on the template Provides ync audio Frame options



Advanced State Tab

Most state parameters have both an Enable and an On/Off control. On/Off refers to whether or not the particular state is controlled in the Shader.

Enabling or disabling a state is only used if the particular type of state control is set to be on. For example if depth control is set to On, this means that the depth buffer tests are affected by this Shader. Then there are two possible options:

Enabled is checked - this means that the depth buffer tests are set by this Shader (because the control is set to on) and the test is set to be enabled.

Enabled is not checked - this means that the depth buffer tests are set by this Shader (because the control is set to on) and the test is set to be disabled.

If a state doesn't specify a value for a piece of state (the control is set to Off), then the state will be set to its default value.

General sub-menu

The general options are added to cut down the complexity of the state editor. For a full description of each option see the relevant section.

Reset:	Enables all of the options below
Backface culling:	Enable / disable backface culling
Lighting:	Enable / disable lighting
Depth test:	Enable / disable depth test
Transparency:	Sets the blending to be SRC_ALPHA, ONE_MINUS_DST_ALPHA
Key:	Sets the alpha blending to be ONE_MINUS_DST_ALPHA, ONE

text1TRFM text1SHDR text1TEXT
text 🔽 🔛 🍇
Shader Material Texture State
General
BESET
Backface Culling
Lighting
Depth Test
✓ Transparency
🗸 Key
Donth Control
Disy fine
Diending
Points
Lines
Polygons
Stencil

Swift



Depth Control sub-menu

Depth Control	
✓ On/Off	Enable
🗹 Depth Mask	
Depth Function	
Lequal	\sim
Near Depth	
0.000000	▲
Far Depth	
	÷

Depth: Alters how and whether depth buffer tests are used whilst rendering.

Depth Mask: Controls whether or not the depth buffer is written to whilst rendering. Default value is true.

Depth Function: Controls the depth test function to use when rendering . Default value is Lequal.

Near Depth: Modifies the smallest possible value in the depth buffer. Default value is 0.

Far Depth: Modifies the largest possible value in the depth buffer. Default value is 1.

Blending sub-menu

Blending		
✓ On/Off	💌 Enable	•
Source Factor		
Src Alpha	-	
Destination Factor		
One Minus Src Alpha	_	
Alpha Source Factor		
One Minus Dst Alpha	•	
Alpha Destination Factor		
One		
Blend Equation		
Func Add	-	

Blending: Controls how rendered pixels are combined with existing pixels already in the output.

Source Factor: Controls how the colour value obtained from the object currently being rendered is used to control the output. Default value is Src Alpha.

Destination Factor. Controls how the colour value obtained from the screen buffer being rendered to is used to control the output. Default value is One Minus Src Alpha.

Alpha Source Factor: Controls how the alpha value obtained from the object currently being rendered is used to control the output. Default value is None.

Alpha Destination Factor: Controls how the alpha value obtained from the screen buffer being



rendered to is used to control the output. Default value is None.

Blend Equation: Specifies an equation used to combine source and destination pixels together. 1 Default value is Func Add.

1 Min or Max overrides any settings for source and destination factors.

Add :Computes the source and destination values using the specified factors and then adds the blended source and destination values together to produce the final output. This is the default mode of operation.

Subtract : Works like add but performs a subtraction of the blended destination value from the blended source value.

Blend Colour: Specifies a colour value to use when a constant blending factor is chosen.



Lighting sub-menu



Lighting: Controls the lighting state underneath the Shader node.

Two sided: Lights both the back side and front side of the object.

Shade Model: Smooth or Flat and indicates whether or not lighting values are interpolated across individual polygons. If the model is set to flat each polygon will be shaded with a single lighting value. Default value is Flat.

Colour Control: Single Colour or Separate Specular. This controls how the specular lighting is applied to the object. With separate specular the texture is modulated with the ambient and diffuse lighting terms and then the specular component is added on top to give a noticeable highlight. Using single colour means that the combined ambient, diffuse and specular terms are used to modulate the texture. Default value is Single Colour.

Operations		
Culling		_
✓ On/Off		🗸 Enable
Face		
Back		▼
Normalise		
🔽 On/Off		💌 Enable
Alpha Test		
✓ On/Off		Enable
Action	Reference	
Notequal		

Operations sub-menu

Culling: Culling refers to the removal of polygons that are not facing the camera during rendering. The culling cuts down on the amount of rendering that needs to be performed and hence improves performance. Culling however only works when an object is a completely closed piece of geometry. Hence in certain situations culling needs to be disabled. A polygon is defined as back facing if the normal of the polygon is facing away from the camera. Front facing polygons are ones whose normal are facing towards the camera.

Normalize: Controls whether the graphics hardware re-normalises the surface normals passed to it. This is used when a supplied piece of geometry does not have unit length surface normals. If surface normals are not of unit length lighting calculations will not behave as expected as they expect unit length surface normals. Visually normals not being correctly normalised will appear as



overly bright lighting with very coarse highlights.

Alpha Test: Alpha test specifies a test function and a test value. Each pixel is evaluated by comparing the current pixels alpha value using the comparison function against the reference value and if the expression evaluates to true the pixel is rendered otherwise it is disregarded.

Action: The comparison function used in the alpha test.

Reference: The value used in the comparison operations.

Scissor Test: Scissor test evaluates each pixel being drawn against a bounding box. If the pixel is inside it is drawn otherwise it is disregarded.

Box: The location and dimensions of the box. The box is specified in screen space coordinates.

Colour Mask: The colour mask specifies which colour channels are written to when pixels are written out to the display. By default all three colour channels and the alpha channel are written to.

Red, Green, Blue and Alpha: Controls which channel is written to.

Points sub-menu



This page controls the parameters for rendering points. These values are only applicable if an object is being rendered using points.

Point Smooth: Controls whether the points are drawn using alpha blending or not to produce smooth edges.

Points Size: Specifies the size to render the point in pixels

Min Point Size: Specifies the minimum size to render the point in pixels

Max Point Size: Specifies the maximum size to render the point in pixels

Distance Attenuation: Specifies constant, linear and quadratic attenuation terms for the point size. The attenuation is based on the distance of the point from the camera.

Fade Threshold: Is a size in pixels which if the size of a point is above it's alpha value will be modulated to fade the point out.

Lines sub-menu: Specifies the width of any lines drawn. This value is only applicable if an object is being rendered using lines.

Line Width: Specifies the width of the line in pixels



Polygons sub-menu

Polygons			
Polygon Offset			<u> </u>
9 Fill	🗶 Line	Point	
			- A
Offset Factor			

Polygon Offset: Polygon offset affects the depth values written to the depth buffer when a polygon is rendered.

Polygon Face Mode: Polygon face mode controls how polygons are drawn - either as filled polygons, lines or points. Lines are drawn for each edge of the polygon or points for each of vertex of the polygon. Different drawing modes can be specified for back and front facing polygons (see for more details on back and front facing polygons).



Stencil sub-menu

Stencil	
✔ On/Off	Enable
Never	✓
Oxfffffff	
Write Mask	
Oxfffffff	
Mask	
Oxfffffff	
Stencil Fail	
Кеер	

This is advanced OpenGL functionality and requires an in depth knowledge of OpenGL to use. *Function*: Stencil test (None, Less, Lequal, Greater, Gequal, Equal, Not Equal, Always).

Reference: Reference value for stencil test.

Write Mask: The stencil bit planes to be written to.

Mask: Used in the stencil test.

Stencil Fail: What to do if the stencil test fails (e.g. Keep, Zero, Replace, Incr, Dec, Invert).
Depth Fail: What to do if the depth test fails (e.g. Keep, Zero, Replace, Incr, Dec, Invert).
Depth Pass: What to do if the depth test passes (e.g. Keep, Zero, Replace, Incr, Dec, Invert)



Playout Editor

Overview

This manual covers the Playout mode of Swift. Playout provides a user interface to play out stacks of templated graphics in Swift. An operator can stack graphics and methods, configure graphic elements (for example, changing text), and play them out. The aim of this manual is to provide the user with the knowledge necessary to operate Swift in Playout mode. This manual assumes that you have already built or been provided with your graphics.

Terminology

This is a glossary of commonly used terms.

Graphic Template

A graphic that is built in design and edit. It is called a template because it expects additional information to be provided before it can be broadcast. For example, a templated lower third strap would be built to accept any text line.

Page

A page is a templated graphic that has been filled out with the relevant information. You can have multiple pages for each templated graphic, and each of those pages can provide different information. For example, a templated graphic that displays a lower third strap may be paged twice, once with the presenters name and one with a story headline. There is no limit to the number of pages that can be created from a templated graphic.

Stack

The stack provides a list of pages in a particular order. These can be played through in order, or out of order depending on your workflow.

Method

A method is part of a templated graphic. Each method will make a graphic behave in a certain way. Some common examples are methods to animate a graphic on, animate a graphic off, and to change the information displayed on a graphic.



Preview

Preview lets you view what a page will look like without taking it to air. This is done by showing only the last frame of the animation.

Object Transition

Playout graphics can be setup to animate automatically when certain graphics are played in sequence. This is achieved using specially named methods, and the process is called Object Transitions. See the design and edit manual for more details.

Workflow

This section describes the steps in the process of bringing graphics from the design stage through to being broadcast live.



Swift Editor

- 1. Add inputs for customization
- 2. Generate interfaces
- 3. Save template

Playout Editor

- 1. Select template
- 2. Modify settings
- 3. Add to stack
- 4. Playout stack live

Playout is one of the interfaces an operator may use to test or play graphics to air on a Swift system. Graphic Templates for Playout are built using Swift. In the final step, the graphic is set up to work with Playout. This involves adding inputs, which allow the graphic to be customised from with the Playout interface. The interfaces that are used within Playout to customise the graphics are automatically generated based on the inputs that you provide. Finally, the graphic template is saved. This graphic is then available in Playout. Once in Playout, an operator selects a template and populates the template with information. A populated template is called a **page**. The page is then added to the stack, and is then ready to be played out. If the operator makes a mistake, he can simply reselect the page in the stack and modify it's contents. To play a page in the stack, the operator selects the graphic to playout, and presses take.

Setup for standalone Playout (with no preview)

A tOG Playout system may be used in various configurations depending on your exact requirements. The following is a typical example of how Playout would be used as part of the Swift Pro solution. The simplest Playout system is a standalone machine, with Swift only. No special setup is required in this case. The operator sees the same live output on their Playout interface as what is seen on the video output.





Manual Operation

Entering Playout Mode/Interface

Playout mode can be activated from the View menu (View->Switch To Playout Mode), or by clicking on the playout icon on the toolbar.

plt

You can also switch to playout mode by pressing the Escape key. You can also launch Swift directly into Playout mode by using the relevant launcher icon.

The interface consists of six main sections

- 1. Preview window
- 2. Control buttons
- 3. Stack
- 4. Graphic templates browser
- 5. Method browser
- 6. Graphic interfaces





There is also a set of tools on a toolbar at the top of the template interface for managing the templates and template directories.



Playout Toolbar

- A Open Project
- B Project Settings
- C Preferences
- D Screengrab
- E Generate icon for current script
- F Performance Dialog
- G Toggle (show or hide) Method browser
- H Toggle (show or hide) User Interfaces
- I Loop stack playback
- J Video attached and detected (turns green from red if detected)
- K Video attached and synchronised (turns green from red if detected)


1. Preview window

The preview window shows graphics on the operators screen. When the operator is taking graphics to air, the preview window will show the same graphics as are going out live. If your system is setup with preview enabled, the preview window will show you the next graphic that is going to be aired.

ТАКЕ	😢 Clear Stack	Load	1 Up	🔀 Clear
IANE	Abort	🐟 Save	🤳 Down	💿 Delete
Layoff				1

2. Control Buttons

TAKE

The take button broadcasts the current graphic or cue's the current graphic if it is on a cue point. The graphic will also appear in the preview window. The button will change from green to red while the graphic is animating. Once the animate is complete the Take button will revert to green. Note that the stack is inoperative while the graphic is animating.

Clear Stack

Clears the stack, but does not abort any running graphics.

Abort

Aborts all graphic. This will also abort all on air graphis. The selection is returned to the top of the stack.

Load and Save

Stack Loads a graphics stack from file and appends it to the end of the current stack.

Up and Down arrows

Moves the currently selected graphic or method up in the stack.

Clear (F11)

Aborts the current graphic and clears the stack. This will stop the graphic from being broadcast.

Delete

Script Deletes the currently selected script from the stack.



Layoff

Render the current stack to a movie file or image sequence.



3. Stack

Script 9	Nack
	a Test1
	cueGraphic
	🔎 bringOn
	● takeOff
<u> </u>	Z Test2
	cueGraphic
	bringOn
	e takeOff

The stack holds a list of graphic instances that are setup and ready to be run. Each graphic shows the name of the graphic, an image representing the graphic, and details of the contents of that graphic.

The graphic that is currently live is highlighted in RED in the stack. The graphic highlighted in BLUE is the graphic that will be taken to next. Usually, this will be the next graphic in the stack, but you can choose a new graphic by clicking it with the mouse.

Selecting a graphic will also make it active for modification via the graphic interfaces, and make it the target for stack manipulation.

4. Graphic template browser



The template list contains all of the graphic templates known to the Swift system. A graphics template needs to be populated with content to make a graphic that can be taken to. For most graphics, content consists of textual content, but also covers alignment of text, the size of font to use, and other aspects of the graphic that are user-definable.

As well as graphics templates, the template list also shows stacks. A stack may hold a single graphic or multiple graphics. These graphics already have their parameters specified and there is no custom interface for a stack. When you drag or double click a stack, it will be expanded into the graphics stack in the same ways as if you had loaded it using the Load Stack button.

The directory tree to the left of the graphics allows you to navigate and manage your graphics. You can create directories in which to store stacks and pages, and you can drag stacks, pages and graphics from one directory to another by dragging between the directories.



5. Method browser

🜗 bringOn	<u>_</u>
🕕 cueGraphic	
🕕 takeOff	

The method browser exposes the methods within the template to the operator.

6. Graphic interfaces

bringOn		
text1TEXT_String		
text1		

When you select a graphic in the stack or in the graphic template list, a relevant interface will open up.

Each interface is custom built for it's graphic to allow the relevant content to be entered. For instance, the example shown to the right is designed for one line straps, and allows you to change the alignment of the text, the text itself, and the font size.

If you select a graphic from the graphic stack the interface will be populated with the values for that graphic. If the graphic was selected in the graphic template list, the interface will keep the values last entered into it.

Note : Some graphics, such as the SubsBug and NextBug graphics have no available options for the user to select. In these cases, the interface will remain on the last interface it was on, and is not used by the graphic.

All of the graphic interfaces have two common buttons at the top. The UPDATE button updates the graphic currently stacked.



Operations

Stacking a graphic

To stack a graphic, you can :

- Drag and drop a graphic from the Graphic List (4) into the Stack (3).
- Alternatively, double click the graphic in the Graphic List (4) The graphic will appear as the last item on the stack.

Editing a graphic

A stacked graphic will display a user interface (6) containing parameters that you can change. The parameters and the makeup of the user interface are set up as part of the procedure for editing the graphic. (For more details, refer to Inputs in the Design and Edit Manual)

Editing the values in the user interface will automatically update the graphic in the stack. In order to see the changes on output, you must take the graphic again.

The current values for all graphics can be seen next to their name in the stack.

Selecting and taking a graphic

Select the graphic that you want to take by clicking on it. In the Stack (3). The selected graphic appears in blue.

To take a graphic, select the graphic in the stack, and press either the green Take button on the operator panel, or press the enter key on the numpad.

Whilst the graphic is animating, the graphic in the stack will turn red. Once it has finished animating, it will turn green.

NOTE - if the graphic has finished, the selection will now point at the next graphic in the stack, and pressing take will take this graphic.

NOTE - Some graphics are multi-stage, and require a number of takes to fully animate.

Rearranging the Stack

Graphics in the stack can be rearranged by:

- Click and dragging a graphic somewhere else in the stack. The graphic will be moved after whichever item you drop it on.
- Alternatively, use the Up and Down Operator Buttons (2)



Clearing Stacked Graphics

To delete a graphic from the stack, select the graphic and click on the Delete Operator Button (2) To abort all graphics and clear the stack, click on the Clear Operator Button (2). Alternatively, you can use the keyboard shortcut F11.

Aborting a Graphic

To abort the currently running graphic, click the Abort Operator Button (2). Alternatively, you can use the keyboard shortcut F12.

Abort will clear all Swift output. You can then run graphics from fresh.

Playing methods

A graphic may contain a number of methods. Each method is a way in which the graphic can be animated. Methods are created as part of the graphic design process. (See Design and Edit Manual, Methods and Blocks in the Timeline Overview)

Any methods that were exported when designing the graphic can be selected and played back directly from the Playout interface.

To view available methods :

- Press the Show/Hide Method Player toggle on the toolbar above the script chooser.
- This shows the Method List. (5)

The method list shows you available methods for the graphic. If this list is empty, the graphic does not have methods.

To stack a method :

• Double click a method to add it to the stack.

NOTE : methods appear indented beneath the graphic that they run on. Methods cannot be mixed with methods from other graphics.

To play a method :

The graphic must have been played first.

Click on the method in the stack, and hit take.

Methods can contain editable parameters, these can be updated in the same way as they are for graphics.



Loading and Saving Stacks

A stack of graphics, including all parameter values, can be saved for use at a later date. To save a stack for later use, click on the Save Stack button. A file dialog will open allowing you to save the stack with the name of your choice.

You can insert a predefined stack or page to the current stack by clicking on the Load Stack Operator Button (2). An open file dialog will appear that allows you top select a predefined stack and load it.

Stack Looping

In some situations it is useful to set a stack of graphics to play automatically and continuously loop. This is useful when testing graphics, or if using Swift in a demonstration mode. Turn on stack looping to do this.

Page Stacks

A page stack allows you to recall one or more graphics by typing in a page number. To create a page stack :

- Setup the stack of graphics as normal.
- Click on Save Stack.
- When asked to give the stack a filename, save it as the page number that you want to recall it on. For example, naming your stack 524 will allow it to be recalled using that page number.

To recall a page stack :

- Hold down the Alt key
- Type the page number of your stack on the numeric keypad.
- Release Alt

NOTE: Calling a page stack will automatically clear any stack that you currently have loaded and replace it with the page stack. The first graphic in the stack will be taken automatically.

The loaded stack will be inserted after the next graphic (highlighted in BLUE on the interface).

If you want the loaded stack to replace the current stack, click the Clear Stack button or press F11 first.

Layoff to disk

You can render a stack of graphics to disk as a movie or an image sequence. In Swift, this is called Layoff. To choose your recording format, open Tog Preferences, and go to the layoff tab.



The user can specify how Swift will layoff graphics to disk here.

🔶 Prefere	nces C:\l	Jsers\Ju	stin\Ap	pData\Re	paming/RTS	oftware/tog2c	lsettings.	ini	<u>?</u> ×
Protocol	Video	Audio	NDI	Locale	Annotations	Run Mode	Layoff	Text Safe Marking	gs
FileNam Default G:\Sak Default Ieague	e Directory ssVideo\G Filename FableOff ss (sws)	raphics as	sets\Clip	\$					
-Layoff T Movie Forma	ype ovie Propertie: at	8) Ima	ge					
Video DN> Audio	Codec (HD Codec	_	_	_					
	lE ⊯NgvsSiz 1	ê I I I I I I	1 1 1	· · ·	Max				
Cue Fra	mes	_	_	-					
								Cancel	Save

Destination Directory

The files are written to this directory.

Destination Name

The files have the form (for an image sequence) <Destination Name>@0000.png.

Format

Choose the file format to layoff to. Image formats will layoff to image sequences, while movie formats will lay off to movies. Recommended image formats are png, jpg, tga. Recommended movie formats are mov, avi.

Swift



Cue Frames

When laying off, Swift does not pause for cues but it will loop on the current frame for Cue Frames.

Separate Alpha

Write the alpha of each frame as a separate file.

Field Render

Combine successive pairs of frames by interlacing their fields.

Odd Field Dominance

Frames are interlaced by using the odd field of the first frame with the even frames of the second. Turning this off reverses this behaviour.

Movie Bit Rate

Sets the bit rate for movies i.e. the smaller the bit rate to poorer the quality and vice-versa

Video codec

If using video, also specify a video format. Depending on your chosen codec, you may want to set the bitrate as well. The following codecs are supported :

Mpeg2

Lossy encoding, can only lay off the fill channel.

Mpeg4

Lossy encoding, better quality at comparable bitrates to mpeg2, takes longer to render. Can only lay off the fill channel.

UNCOMPRESSED

Uncompressed, Fill channel only. Best quality but very big filesize.

UNCOMPRESSED+A

Same as UNCOMPRESSED, but also saves the Alpha channel.

HUFFYUV+A



Lossless compression, Fill and Alpha channel. Roughly half the fileszie of uncompressed.

You will notice in your graphics list, two graphics called LayoffStart and LayoffEnd. Drop Layoff start into the stack at the point at which you want to start layoff, and layoff end at the point when you want layoff to finish.

Select the LayoffStart graphic. In here, you can

NOTE: the destination directory and destination name in preferences are not used when laying off from playout, you set these in the stack itself - see below.

NOTE: For more information on layoff formats available, see the Design and Edit manual.

Controlling Multiple Playouts

TOG Playout systems can be set up to communicate with each other, allowing synchronised output from multiple machines from a single user interface. It can also allow multiple user interfaces to control a single live machine.

When using playout, the common protocol to use is the Render protocol. To set this :

- Open preferences.
- Go to the protocol tab
- Set the protocol to Render

Some examples of when you would connect multiple Playout systems together :

- A multi-camera VR set. Each camera output is rendered using a seperate Swift machine. The operator controls all cameras from a single machine.
- A newsroom system. A tOG Playout machine may be controlled directly, as well as from multiple other content providers withing the system.
- When preview is a requirement, two Swift machines can be connected. One will be set up as a Preview machine, the other will be set up as the Broadcast machine. They will communicate to provide preview/live functionality.

Render mode in Swift allows the user to connect Swift to other tOGs. The render mode makes this seamless from the user's point of view. A tOG playout system can be either a Master or a Slave. A master controls the user interface, and tells the Slave what to render. A Slave can accept connections from multiple Masters.

Port Number

The port number for socket connections between the systems.

Address



The server address. This is only required by a Master, it is blank for a Slave.

Examining the Scenegraph

It is sometimes useful when testing graphics to view the scenegraph from within playout. NOTE: This functionality is provided for testing purposes only. Changes made to the

scenegraph are not saved once the graphic is cleared. Shader changes can be saved. Making modifications to the scenegraph from within playout is allowed, but the results can be unpredictable and may cause the system to crash or hang. Do not use the scenegraph view from within playout on a mission critical machine.

To view the scenegraph, Press F9. For more information on the scenegraph, see the Design and Edit documentation.



Document Summary

This manual has covered the Design & Edit mode of Swift in varying levels of detail. After completing training and tutorials, the user should be familiar with basic operations in Swift and be able to use this manual as reference and procedural support.

Further Reading

Following this guide, the reader is advised to read another manual that relates to the function he wishes to perform in Swift. The other available manuals are:

Manual	Description
Live Manual	For operation of Swift controlled from external applications
VR Manual	For using Swift in a VR situation
tOG Sports Manual	For using tOG in a Sports situation



APPENDICES

1 - Recommended XDCAM asset prep

The purpose of this appendix is to outline and detail the steps required to produce MXF wrapped XDCAM assets for use with Swift graphics tools.

Using ffmpeg from the command line:

For Movies without embedded audio

In this example a clip called Show_01_Footage.mov will be transcoded to a clip called output.mxf:

ffmpeg -i Show_01_Footage.mov -pix_fmt yuv422p -vcodec mpeg2video -non_linear_quant 1 -flags +ildct+ilme -intra_vlc 1 -qmax 3 -lmin "1*QP2LAMBDA" -rc_max_vbv_use 1 -rc_min_vbv_use 1 -g 1 -b:v 50000k -minrate 50000k -maxrate 50000k -bufsize 8000k -an output.mxf

For image sequences

In this example an image sequence starting Footage_00001.png will be transcoded to a clip called output.mxf:

ffmpeg -f image2 -i "BS40702_%05d.tga" -pix_fmt yuv422p -vcodec mpeg2video -non_linear_quant 1 -flags +ildct+ilme -intra_vlc 1 -qmax 3 -lmin "1*QP2LAMBDA" -rc_max_vbv_use 1 -rc_min_vbv_use 1 -g 1 -b:v 50000k -minrate 50000k -maxrate 50000k -bufsize 8000k -an output.mxf

Note: Ensure that smart quotes is turned off



Using Adobe tools:

From After Effects Render Queue

Once you have added your comp to the Render Queue, choose the following settings from the Output Module, Main Options tab.

Format

In the Main Options:

- Format drop-down menu list
- Choose MXF OP1a. See below:

Format:	MXF OP1	3		 ✓I 	lude Project	: Link	
st-Render Action:	None			× _ 110	lude Source	XMP Metada	ta
Video Output —							
Channels:	RGB		▼		Fo	rmat Options	
Depth:	Millions	of Colors	-		XDCAMHD 5 Spatial Qual	0 PAL (4:2:2)	
Color:	Premultip	lied (Matte	ed) 🔻		sharrar Sarr	ny – 200	
Starting #:							
Resize							
Сгор							
udia Output Off							



Audio

This format is **not** compatible with audio. Please see section on creating clips with embedded audio, later in this appendix.

• Ensure the Audio Output is off. See below:

Format:	MXF OP1	3		🗹 I clude Project Link	
Post-Renuer Action:	NOTIC			Linclude Source XMP Me	tadata
Video Output —					
Channels:	RGB			Format Op	tions
Depth:	Millions	of Colors		XDCAMHD 50 PAL (4:2	
		lied (Matt	ed) 🔻	Spatial Quality = 100	
Starting #:					
Resize					
Crop					
Audio Output Off					

Video Output Module

In the Video Output Module, click the Format Options from the drop-down menu.

- Select XDCAMHD 50 PAL (4:2:2) Video Codec. See below:
- Click OK





From Media Encoder

Once you have launched Media Encoder:

Format for clips with no embedded audio

• Choose MXF OP1a

▼ Export Settin	gs			
Format:	MXF OP1a	•		
Preset:	XDCAM HD 50 PAL 50i	•	± 🇯	
Comments:				

• Choose the XDCAMHD 50 PAL 50i (4:2:2) codec

		XDCAM HD 35 NTSC 30p
		XDCAM HD 35 NTSC 60i
		XDCAM HD 35 PAL 25p
		XDCAM HD 35 PAL 50i
		XDCAM HD 50 NTSC 24p
		XDCAM HD 50 NTSC 30p
		XDCAM HD 50 NTSC 60i
		XDCAM HD 50 NTSC 720p60
	_	XDCAM HD 50 PAL 25p
		XDCAM HD 50 PAL 50i
•		XDCAM HD 50 PAL 720p50
		-

Disable audio

• Ensure that the audio is turned off



Out	Dutput Name: 13_TXTAUDIO_1.mxf							
✓ Ð	✓ Export Video Export Audio							
•	Summar	у						
	Output: C:\Users\tog\Desktop\13_TXTAUDIO_1.mxf 1920x1080 (1.0), 25 fps, Upper, 00:00:05:00 No Audio							
	1920x1080 (1.0), 25 fps, Progressive, 00:00:05:00 48000 Hz, Stereo							
Effects	Video	Audio	Captions	Publish				

Advanced Options

- Further options allow for correct settings for GOP parameters
- Check Force Fixed-length GOPs
- Check Force Closed GOPs

Effects Vi	ideo Auc	lio	Captions	Publish							
	Frame Rate: 25										
	Field Ord	der:	Progress	sive	Upper First						
	Asp	ect:	Square Pi	xels (1.0)	•						
Rende	er at Maxim	ium D	epth								
Set S	tart Timeco	de to	Zero								
Enabl	Enable Smart Rendering codec										
▼ Adva	nced MXF	Setti	ngs								
Edit Unit	s Per Partiti	on:	• Default		Custom						
	Custom Value: 240										
▼ Adva	Advanced XDCAM Settings										
✓ Force	Fixed-leng	th GO	Ps								
V Force	Closed GO	Ps									

Field rendering

There are 2 options that are available for movie output:

- XDCAMHD 50PAL 25p
- XDCAMHD 50PAL 50i



• Choose the correct option for your requirements



For clips that require embedded audio

• Choose the DNxHD MXF OP1a format



• Select the DNX 36 1080p 25 Preset



• Use the Default Audio settings

Outp	ut Name:						
	port Vide	o 🗸 E)	kport Audio				
▼ S	ummary	,					
C)utput:	C:\Users\tog\Desktop\dnx op1a.mxf L920x1080 (1.0), 25 fps, Progressive, 00:00:04:00 Farget 36 Mbps 48000 Hz, Stereo, 16 bit					
S	Source:	Sequence, 1920x108 48000 Hz,	dnx op1a 0 (1.0), 25 f Stereo	ps, Progre	ssive, 00:00:04:	00	
Effects	Video	Audio	Captions	Publish			
	asic Aud	io Setting	ıs				
Audi	o Codec:	Uncomp	ressed				
Sample Rate: Channels		48000 Hz					
		Stereo 💌					
Sam	ple Size:	• 16 bit			24 bit		

• Use the Default Video settings

Page 162



2 - Evaluating movie files

Broadcast creatives and branding design agencies are the traditional sources of approved assets that inevitably result in a kit of parts for use in automated playout graphics solutions. One of the most common asset types in any kit of parts, is the .tga image sequence.

This universal file format and approach is common practice. The resulting workflow with .tga image sequences has been:

- Design team creation and approval of brand
- Asset and image sequence generation
- · Image sequence provision to playout services as part of kit of parts
- Importing image sequences into playout solution editors
- · Creating proprietary video clips from the image sequences
- Automation template authoring with the resulting proprietary video clips
- Transmission of templates
- This cycle continues when further .tga image sequences are delivered by creative.

Why are .tga image sequences supplied at all?

- They are a standard output format shared by all content creation applications
- · Nearly all graphics departments can output this format
- · Nearly all playout solutions can interpret this format
- The image sequences can be rendered into a proprietary video clip for tx
- They carry an alpha (transparency) channel information
- The transparency channel (alpha) can be rendered into a luma matte in the proprietary format for playout

Why not supply movie files instead of .tga image sequences?

- There are only a few codecs that support a transparency (alpha) channel
- The playout solution does not utilise transparency in one channel, but uses another channel as a luma matte.
- The playout solution does utilise transparency in one channel, but is required to pre-render into a proprietary format.
- Movie files with or without transparency (alpha) channel can contain prohibitive data rates for playout when rendered using standard content creation applications.



Recommended video clip formats

Video clips without alpha

- MXF OP1a
 - $_{\odot}$ XDCAMHD 50 PAL (4:2:2) preset for clips with no embedded audio
- DNx HD MXF OP1a
 - DNX 36 1080p 25 preset for clips with embedded audio

All with the following specifications:

- HD Resolution
- 1920 x 1080 square pixel
- Upper field or progressive
- 25 fps (or 50 fields per sec)
- Maximum data rate <100mbs/sec
- Recommended data rate <50mbs/sec

Advantages

- Low data rates
- Small file sizes
- Disadvantages
- Compression may be visible on subtle colour gradations

Video clips with alpha

- Quicktime wrapper
- Animation codec
- HD Resolution
- 1920 x 1080 square pixel
- Upper field or progressive
- 25 fps (or 50 fields per sec)
- Maximum data rate <100mbs/sec
- Recommended data rate <50mbs/sec



Advantages

- Carries alpha channel if required
- Animation codec common output format

Disadvantages

· Can have prohibitively high data rates

Establishing data rates for Quicktime movies

These movies may contain an alpha channel.

To check the data rate of your movie:

- 1. Open the movie in a Quicktime player
- 2. Go > Show Window (Ctrl I)
- 3. Go > Show Movie Inspector
- 4. View the Data Rate setting in mbits/sec

Ensure that this rate is no higher than 100 mbits/sec

We recommend that the bitrate should be lower than 50 mbits/sec

Establishing data rates for MXF movies

These movies do not support an alpha channel

To check the bitrate of your movie:

- 1. Open the movie in VLC
- 2. Go > Tools
- 3. Go > Media Information
- 4. Select the Statistics tab
- 5. View the Input and Content bitrates in kbits/sec

Ensure that this rate is no higher than 100 mbits/sec

We recommend that the bitrate should be lower than 50 mbits/sec

Establishing the codec used for Quicktime movies

To check the codec of your movie:

1. Open the movie in a Quicktime player



- 2. Go > Show Window (Ctrl I)
- 3. Go > Show Movie Inspector
- 4. View the Codec setting



Establishing the codec used for MXF movies

To check the codec of your movie:

- 1. Open the movie in VLC
- 2. Go > Tools
- 3. Go > Media Information
- 4. Select the Codec tab
- 5. View the codec information provided

Using master and matte movie clips in Swift

Once you have established that your movies data rate is too high, the following become requirements:

- You will require a master (or foreground) movie clip
- You will require a matte (or alpha) movie clip

The approach will be to use both of these two clips in Swift in a matte and master shader configuration.

Step 1: Creating a master video clip

Use the supplied movie clip (or the .tga image sequence) to create a new movie clip that does not contain an alpha channel. See above for recommended codecs.

If you are using Adobe Media Encoder, we recommend:

MXF OP1A with: XDCAMHD 50 PAL (4:2:2)

Step 2: Creating a matte image sequence

Before we can make a matte movie with ffmpeg, we need to create the image sequence that will supply it with the frames we need.

Evaluating the supplied alpha channel or matte image sequence

Whether the matte has been supplied as an alpha channel within your movie or as a separate image sequence, we will need to establish whether it requires inverting before we encode using ffmpeg.

Here is an example:





Fig 1

Fig 2

If the checkerboard portion of Fig 1 shows the area you want to *punch through* to reveal other parts *behind* your movie, then you might expect Fig 2 to be the result of your matte movie once you have created it.

Inverting the matte

However, if this is the case, then your matte will need to be inverted. See Fig 3 and Fig 4:



Fig 3

Fig 4

Fig 3 and 4 represent a matte where:

- The movie that it is applied to will appear in black portions or checkerboard portions of the matte
- The parts of the graphic that will revealed by the movie matte are the white portions of the matte.
- Always consider the white portions of your matte to be *punching a hole* through your movie clip.

Rendering your matte image sequence

- Use the guide above and the tools you have at your disposal to create a sequence of either black and white images as in Fig 3 or alpha images as in Fig 4.
- These can be saved off as either .png or .tga files.



Using ffmpeg to create a matte movie

ffmpeg can create a Quicktime grayscale movie of only 256 colours. This is not possible in most, if not all other commercially available applications such as Adobe or Autodesk.

Working example

We are going to create a matte movie from an image sequence located in a folder within a directory on our desktop

Open a command prompt at the correct location

Within the command prompt, navigate to your folder that contains your matte image sequence using commands, for example, from the prompt:

C:\Users\Tog>

Type:

- cd C:\Users\tog\Desktop\testclips\whiteMovingOnBlackNoAlpha
- Press Return on the keyboard. See below:



Adding your image sequence

Type:

ffmpeg -f image2 -i "whiteMovingOnBlackNoAlpha_%05d.tga" -vcodec qtrle -pix_fmt gray out.mov

Image sequence number

Image sequences are always numbered before the file extension. We need to tell ffmpeg how many digits the sequence name carries.

For a sequence filename that begins: whiteMovingOnBlackNoAlpha_00001.tga, the command is:

"whiteMovingOnBlackNoAlpha_%05d.tga"

Where ffmpeg is instructed to look for 5 decimal places in each of the image sequence files.



Output file name

The output file name in the command is the final component. In the example above, the output name is:

out.mov

The file will be output to the same folder as the image sequence.

Do I transcode?

Is the data rate of your clip >100mbs/sec?

Yes: Transcode the clip to one of the formats stated above and create a separate movie for the matte channel

No: See below

Is the data rate of your clip <120mbs/sec but >80mbs/sec?

Yes: Consider transcoding the clip to one of the formats stated above and create a separate movie for the matte channel

Consider if your ICE is using dual dll's.

If you are required to transcode your assets:

ffmpeg

https://www.ffmpeg.org/

This is open source and free to download

It is appropriate to use standard encoding software such as Adobe Media Encoder or similar to encode the *master* or *foreground* channel, but ffmpeg will be required to create the matte channel.



3 - Supported formats

Input formats

Input wrappers

- avi
- mov
- mxf(op1a)
- mpg
- mp4
- m4v
- wmv
- dv
- flv

Input Codecs

- WMV1/2/3
- mpeg
- mpeg2
- mpeg4 pt2
- mjpeg
- H263
- H264
- ProRes
- AVC50/100
- DNxHD
- HuffyYUV
- MJpeg
- FLV
- VC-1
- DV25/50/100

Swift

Page 171

• YUV420/2 (raw)





Output Formats

mpg

- mpeg1
- mpeg 2

avi

- mpeg1
- mpeg2
- mpeg4
- mjpeg
- flv
- YUV422
- BGR
- BGRA
- Huffyuv
- Huffyuv+alpha
- targa
- dv DV25/50/100*

mxf

- DV25/50/100*
- AVC50/100*
- DNxHD
- mpeg2

mov

- qtRLE(animation)
- mjpeg
- mpeg2
- dnxhd

flv



• flv

tmv

• tOG internal format

Notes:

Standards are:

- PAL
- NTSC
- 720p
- 1080i
- 1080p

From Sports, clips will be Upscaled/Downscaled to the currently configured standard.

• IntraFrame is preferred (GOP 1)

Standards denoted * are only available with MainConcept License



4 - Cue Margin

Adding cueGraphic methods to templates for ICE

What is the cueGraphic method

The cueGraphic method is a method in an RT advanced graphic. It is sometimes necessary or beneficial to add this extra method to templates and take advantage of the ICE configuration Cue Margin setting.

Why use the cueGraphic method

The cueGraphic method is a method that enables the pre-loading and resetting of a variety of dynamic content. For example, templates that need external information or data - such as rss, xml, database queries as well as internal large or multiple movie assets. ICE runs this method - if it is present - to ensure that these assets or information/data are cued and ready to play before the bringOn is called.

How to add a cueGraphic method in the 2d editor

- Open your template and click the add new method button
- Type cueGraphic as the new method name

Adding or moving components to the cueGraphic method

If you have something that you want to place in the cueGraphic method, any animators, inputs or user code connected with it must also be placed in the cueGraphic method as well as being extracted from the bringOn - if it was present to start with.

Using cueGraphic method with movie clips

If you have a movie clip that you want to place in the cueGraphic method, any inputs or user code connected with that movie clip must also be placed in the cueGraphic method as well as being extracted from the bringOn - if it was present to start with.

Preparing the cueGraphic method

- Adding a Reset Animator
- · Select the cueGraphic method in the drop down menu
- · Select the node in the scenegraph with the movie clip
- Select the Shader tab
- In the ResetMovie bar, click the Add Animator button

Page 175



Moving Inputs

• If there is an input on this movie clip - for example it is supposed to be dynamic - then move the input from the bringOn to the cueGraphic method

Moving user code

If there is any user code applied to the use of this movie clip - for example it is supposed to be in different positions under certain circumstances - then cut the corresponding user code from the bringOn and paste into the cueGraphic method

Saving the graphic

• Go to the bringOn method and Save the graphic

Setting the Cue margin in ICE Configuration

Launch the Snell ICE Configuration editor

Snell ICE Configu	uration
General Automation	Interface Media Store VBI Sources Channels Outputs Encoders Scaling Rt Graphics Script Triggers Engineering
Number 1	<u>-</u>
	·
Rtg	
	Dhak parea Excelone
	Eparuane 405/04/2
	Resolution HD Show preview window
Mixer sec	juence position 3 🕂 Input count 2 🕂 APC limit 199 🕂 🕻 Cue margin 10 🕂
<u>B</u> egin event	method names
End event	method names
	✓ Downstream Mode ✓ Persistent Mode
	Default project D:\RTSW\projects\ICE_Demo_1\ICE_Demo_1.prj 😂
	nelam Subr
Layers	
Name	Default script Begin End Add
Layer 1	GraphicLayer1
Layer 2	GraphicLayer2 Edit
Layer 3	GraphicLayer3
Layer 4	GraphicLayer4 = Delete
Layer 5	GraphicLayer5
Layer 6	GraphicLayer6
Layer 7	Graphic aver/
Layer o	GraphicLayero
Laver 10	MotionGraphicaper 2
Laver 11	MotionGraphicLaver3
Layer 12	MotionGraphicLayer4
Apply	Diagram Export to Morpheus Save Load

Set this margin in *frames*

For example 50 frames is a 2 second cue margin that will reset the movie clip before the



bringOn is called

Click Apply and close the Snell ICE Configuration editor