Sentinel Licensing

About	Description
Revision	1.2
History	October 2022; Feb 2023
Authors	S Hart, Jerry Clark

Overview

This document outlines the various ways to request, apply and transfer software and hardware* licenses. It also covers some troubleshooting steps



*Hardware USB license dongle

Requesting a Trial License

If you require a license to trial the software (Tactic, Swift...), please contact the sales team to obtain a trial license by emailing sales@rtsw.co.uk

Requesting a license from within the application

To request a license, you need to launch the software you need to license for the first time (Swift, Tactic etc...) and you should be presented with a window advising that the license is missing:



Click on "OK"



Click on "License"

License Requester		? ×
Activate		
Install a Licence		
Use this to install a new	licence supplied by RTSoftware Ltd (.v	2c file)
If you are updating a lice plugged into this PC and	nce on a USB Security Key (or Dongle) d that it is lit	ensure this is
	Apply Licence (v2c)	
Request a Licence		
Use this to request a ne RTSoftware Ltd (.c2v file	w licence or to update an existing licen). Send the request (.c2v file) to suppor	ce from t@rtsw.co.uk
If you are requesting a li plugged into this PC an	cence for a USB Security Key (or Dongl d that it is lit.	e) ensure this is
	Create Request (c2v)	
Renglish	•	Close

Click on "Create Request (c2v) and save the *.c2v file into your computer, please send that file to $\underline{license@rtsw.co.uk}$

Applying a License

Using the same steps above to create a request, when you are provided with a v2c license by RTSW, please click on "Apply License (v2c)", you will see a confirmation box and then will be able to proceed with launching the software.



Software License Transfer

If you need to transfer your active license from a machine to another (only applies to Software Licences, trial software licenses are excluded), you will first need to install the same software on both machines.

In the new target machine (where you're intending to move the license to), launch the software and you will be advised that the computer doesn't have a valid license as per the below screenshot:



Click on "OK"



Click on "License"

License Requester	?	\times
Activate Transfer		
Transfer a Licence		
Use this to transfer your current licence from your old PC to a new PC. this only applies to Software Licences and not Trial Licenses or a USE Key (or Dongle).	Note that 3 Security	t V
1. Install this software on the new PC (as well as your old PC)		
2. On the new PC, collect details of the new PC that you want to transfe licence to (.id file)	er the	
Collect Info (id)		
3. On the old PC, use the details of the new PC (id file) to create a tran licence (.h2h file)	isferable	
Transfer Licence (h2h)		
4. On the new PC, install the transferable licence (.h2h file)		
Apply License (h2h)		-
Renglish 💌	Cl	ose

Navigate to the "Transfer" tab and click on "Collect Info (id)" to save the *.id file.

You will need to copy the *.id file to the other machine where the active license exists as it's needed for the transfer process.

Now, on the machine where the license is active, from within the software when it's running, click on the cog wheel settings button and select "Show License Details"



Click on "License"

🔌 License Details		×
Current Time Fri Jun 11 14:15:24 202	1	
Device ID 1		
Product		
Feature	Status	
HEARTBEAT	PERPETUAL	
RTU_ENABLED	PERPETUAL	
RTU	Sat Dec 31 23:59:58 2022	
EDIT	PERPETUAL	
2DEDIT	PERPETUAL	
PLAYOUT	PERPETUAL	
LIVE	PERPETUAL	
PREVIEW	PERPETUAL	
VIDEO	PERPETUAL	
4K	PERPETUAL	
ТОИСН	PERPETUAL	
MAPS	PERPETUAL	
KEYER	PERPETUAL	
	PERPETUAL	
SPORTS	PERPETUAL	
RECORD	PERPETUAL	
ANALYSIS	PERPETUAL	
	PERPEIUAL	
PECOPDIONICEFT	DEDDETIIAI	
EFATURETRACK	DERDETIAL	
OUICKTRACK	PERPETIAI	
2DTRACK	PERPETUAL	
VR2D	PERPETUAL	
	Ok	
License		

*The above example is for illustration only, your license details may vary.

Navigate to the "Transfer" tab and click on "Transfer Licence (h2h)"

🖘 License Requester	?	\times
Activate Transfer		
Transfer a Licence		
Use this to transfer your current licence from your old PC to a new PC.N this only applies to Software Licences and not Trial Licenses or a USB Key (or Dongle).	lote that Security	t 7
1. Install this software on the new PC (as well as your old PC)		
On the new PC, collect details of the new PC that you want to transfer licence to (.id file)	rthe	
Collect Info (id)		
3. On the old PC, use the details of the new PC (.id file) to create a trans licence (.h2h file)	sferable	
Transfer Licence (h2h)		
4. On the new PC, install the transferable licence (.h2h file)		
Apply License (n2n)		
R English	Cl	ose

Browse your computer and select the *.id file that you've previously generated in the new target computer. Once that's done, a new file will be created and it will be created with a *.h2h file extension, this file needs to be sent to the new target computer.

On the new target computer, follow the initial steps to get to the "Transfer" tab and this time around, select "Apply License (h2h)", once that's done, your new computer will be licensed. Note that the other computer wouldn't be licensed anymore as the license was transferred over to the new machine.

Web Portal

The web portal is an online browser tool that you can use to either apply a product key, update an existing key or download a key for a different machine

Applying a License Using the Web Portal

If you were provided with a "Product Key", please visit the following URL: <u>https://licensing.rtsw.co.uk/ems/customerLogin.html</u>

RT software	
Customer Portal Login	License Update
Product Key: Log In	
© 2021 RTSoftware Ltd. All Rights Reserved English Italiano Русский Français 中文 De	d. Support eutsch Español 日本語

Copy/Paste the provided key into the "Product Key" field and click on "Log In". You should see a message confirming that your license has been activated.

Updating a License

NOTE: This process DOES NOT update the software itself to a newer version, it only updates the license.

You can use any of the methods shown previously to apply a new license or use the web portal to update your license if an expiry date has been extended or new features/products have been added to your license.

Once RTSW Support has confirmed that your license has been updated, please visit the same web portal (Link) and select "License Update" > "Update Licenses". A confirmation message will appear to confirm that the update has been applied.



RUS Tool

The RUS (Remote Update Software) tool allows you to apply the same operations as above but using a stand alone tool. This is only available on Windows PC's. It is normally used for customers of our embedded DLL product.

Requesting a License Using the RUS Tool

For DLL customers, please use the RUS Tool that you can download from the FTP website (the file is located inside /Downloads/Software Releases/LicenseUtilities/Win/Gemalto/RTSWLicenseTool.exe)

NOTE: Ensure you have also installed the relevant version of 'togpre from our FTP site.' This installer will be of the form togpre-X.X.X-xxxxx-windows-installer.exe. It is located in the software download section of our ftp site

If you don't have access to the FTP site, please request an account by contacting support@rtsw.co.uk

RUS			-	×
Collect Status Information	Apply License File	Transfer License		
	RTSoftwa	are Ltd		
	License www.rtsw.c	Tool to.uk eys		
	13:46:30 Could not access Sentine Key with specified ID): el protection key! was not found		
	13:46:56 Fingerprint ret Save process ca	5: rieved. anceled!		
Collect information from this (computer to enable:			
Update of existing protect	tion key			
Installation of new protect	tion key			
Collect Information				

In the "Collect Status Information" tab, select "Installation of new protection key" and click on "Collect Information", this will allow you to save a *.c2v file. Please send the file to license@rtsw.co.uk

Applying a License Using the RUS Tool

Using the same tool, choose the "Apply License File" tab and click on the 3 dots to browse and select the v2c file that was provided by RTSW.



Once the field is populated with the file path, click on "Apply Update".

Licence Transfer Using the RUS Tool

You will need the software to be installed on both old and new computers (alongside the Sentinel licencing drivers), you also need the RUS tool on both machines.

			-		
ollect Status Information	Apply License File	Transfer License			
ransfer (rehost) a licens nputers. On each comput	e from one computer to ter, select the Transfe	another, you run the Ri r License tab and perfo	US program orm the appr	on both opriate st	ter
Collect information abou	it the recipient computer	r.			
step 1: On the compute collect and save informa	er to which you want to ation about the compute	transfer the license (the r.	recipient o	:omputer"),
Save recipient informat	ion to				
		Collec	t and Save I	informatio	n
Generate the license tra	insfer file				
Step 2: On the compute the license to transfer, r	er that currently contains read the recipient inform	s the license (the "source nation file and generate	e computer' a license tra	"), select insfer file.	
Кеу Туре	Key ID	Products			
Read the recipient infor	mation file from]	
Read the recipient inform Generate the license tra	mation file from]	

1/ In the new machine, open "Rus Tool", click on "Transfer License" and click on the 3 dots button to save an *.id file, the "Save recipient information to" field will then be populated with the file path.

2/ Click on "Collect and Save Information", this will save the *.id file that you will need to copy to the source machine (the machine with the active license to transfer to the new machine).

3/ In the machine that contains the active license, use the "RUS Tool" and click on "Transfer License". The active license should appear in the middle box and you should be able to see various information about it (Key ID, Products..)

4/Browse your computer to select the *.id file collected from the new machine and add it to "Read the recipient information file from" by clicking on the 3 dots button to select the file.

5/ In "Generate the license transfer file to", click on the 3 dots menu to select where to save the *.h2h file

(License file). Once the file is saved, copy it over to the new machine.

6/ In the new machine, using the RUS Tool, activate the license (h2h file) by clicking on "Apply License File" and browsing the computer to select the h2h file that was generated in the old machine. Click on "Apply Update" and this would apply the license in the new machine

Collect Status Information	Apply License File	Transfer License		
				٦
Indata Eila				1
			10.00 TX	
Ampletindate				

Using a Network License

If you have been issued with a network licence then you can use this remotely by selecting the option in the licence dialog when the product runs up.



You can use either an IP address or a hostname if you know it. This only applies to software licenses

VPN Access using a network license

If you are on a VPN into a server running a network license then you must configure the remote server.

Open a browser and go to

http://localhost:1947

From the web page select 'Configuration:

Sentinel Admin Control Center					
	Admin Control Center F				
Sentinel Keys	Welcome to the Admin Control Cent Note: You can select the language i				
Products	> The Admin Control Center enable:				
Features	 All the Sentinel protection ke The number of users current The Features to which each The users who are currently 				
Sessions	Note: SL UserMode keys are only d				
	> You can perform actions, such as:				
Update/Attach	 Detaching a license from the Cancelling a detachable licer Installing an update to a licer 				
Access Log	> You can implement and manage c				
	> You can make basic configuration				
Configuration	 Setting the display refresh tin Configuring access permissic Defining values for Products 				
Diagnostics	> The Diagnostics page enables you				
	Related Topics Security Considerations Cloud Licensing Detaching Licenses - Overview				

Enter the IP address or the hostname of the machine that is serving the license and press 'Submit'

Sentinel Admin Control Center						
	Configuration Host Nan	ne: vincent				
Sentinel Keys	Basic Settings	Users	Acces	s to Remote License Managers		
Products	Allow Access to Remote Licens	ses	✓ @	You may experience a delay of a few m		
Features	Broadcast Search for Remote I	icenses	~ @			
Sessions	Remote License Search Param	ieters	myhostname.r 192.168.100.	tsw.co.uk 99		
Update/Attach						
Access Log						
Configuration			Submit	Cancel Set Defaults		
Diagnostics						

You should now be able to connect using the remote license over VPN

Detach License

It is possible to detach a license instance for a set period of time from an existing license key. In order to do this a number of prerequisites must exist:

- 1) The license must have been created with network enabled
- 2) The license must have been created with a concurrency limit
- 3) The license must have been created with the 'detach' option enabled
- 4) Detachment must be enabled in the ACC on the machine that is hosting the detachable license.

A license may be detached and applied to another offline machine for a specified number of days. At the end of the period the detached license will expire and the network license will automatically revert back to the original number of licenses available. A license may be detached on line (if the destination machine is on the same network and already has the sentinel driver loaded), or it may be detached for off line transfer using a process similar to 'Transfer' above.

Creating a Detachable License

See "Software Licence Administrator Guide (Internal)"

Enable Detachment in ACC

Before you can detach a license you will need to enable this on the host machine on which the license resides..

Open up a web browser and navigate to

http://localhost:1947/_int_/ACC_help_index.html

Select Configuration->Detachable Licenses

Sentinel Admin Control Center							
	Configuration Host Name: br	ough					
Sentinel Keys	Basic Settings Users	Access to Remote License Managers	Access from Remote Clients	Client Identities	Detachable Licenses	Network	
Products	On-Demand Detaching of License	5					
Features	Enabled						
Sessions	Maximum Duration @	10 days					
	Automatic Detaching of Licenses						
Update/Attach	Enabled						
Accession	Allowed Offline Duration @	2 hours					
, 100000 20g	Common Detach Settings						
Configuration	Reserved Licenses @	0 but at least	0 % of total licenses				
Diagnostics	Per Product Settings	Configure					
		Submit Cance	I Set Defaults				

Enable Detachable licences and specify the maximum number of days a licence may be detached for. (This is NOT the value you will use, it is just the max value available) Uncheck Automatic Detachment. Press the Submit button

Detaching a License

Navigate to the license you wish to detach and select 'Products'

Providing the license was created with detachment enabled you should see an option to select a product on the key and detach it. Note that the 'Available' count will not include any licenses that are currently in use. If there is only 1 license for a product and this is in use then there will be no value shown in Detached/Available.

Product Name	Vendor	Location	Detached	Available	Actions
Tog	4 30308	Local		1	Detach Features
Swift	6 30308	Local	1		Extend Features
TogDLL	4 30308	Local		1	Detach Features
TogDataServer	⇔ 30308	Local		1	Detach Features
TogRepository	4 30308	Local		1	Detach Features
TogMediaWatcher	e 30308	Local		1	Detach Features
TacticLite	4 30308	Local		1	Detach Features
TacticAdvanced	4 30308	Local		1	Detach Features
TacticPro	4 30308	Local		1	Detach Features

Filter by: Key:320854641597326131 | Vendor:30308

In the example above you can see that the key has 9 licensed products and one (Swift) has already been detached. Select the product you wish to detach. You should now see the following

There are a number of ways to select the machine that you want to detach the licence to - the destination machine.

- 1) Destination machine is on the network. If the destination machine is on the same subnet as the host machine then it will automatically appear in the drop down list shown in A above.
- 2) If the destination machine is not on the network then you can add the machine to the host using the destination machine id. Refer to the section on 'License Transfer' for details on how to collect a machine id. You can then import the id file onto the host machine using the 'Update/Attach' section of the ACC. Once you have done this it will appear in the drop down list above

Detach License Host Name: vincent					
Product	TacticLite (ID:9)				
Vendor	30308 (ID:30308)				
Available Licenses	1 available for detaching				
Max. Duration	14 days				
Sentinel Key	820630612125071837				
License Host	Local (only offline detach is possible)				
Detach Method:	(Online Detach is not possible because this is a local product)				
Online	Detach license as an H2R file for use on the recipient machine selected below:				
Offline	chimera				
Concurrency: Total Number of Seats: Expiration Date for De B Comment (optional):	Allow Concurrency for Detached Licenses Detach of multiple seats is allowed only for a cloud license with a limited number of seats. tached License: Day: 4 Month: 11 Year: 2022				

Once you have selected the destination machine you should fill out the expiry date of the detachment in section B above. Once this is done select Submit. This will detach the license and present you with the following screen:

Detach License Host Name: vincent

Recipient Name	chimera
Product	TacticLite (ID:9)
Vendor	30308 (ID:30308)
Sentinel Key ID	820630612125071837

License successfully detached for offline use. Save the H2R file and transfer it to the recipient machine:

Save As ...

A backup of this H2R file can be found in the 'detached' directory of the hosting License Manager. Filename: $20221103_130626_0001.h2r$

Save the H2R file to disk.

Copy the file to the destination machine and apply it using either 'Update/Attach' tab on the ACC. This will install the license onto the destination machine. The license will be valid for the period you specified. You will see that the product is shown as detached on the host machine as displayed in the first image above. When the detached period expires, the licence will automatically return to the host machine and be invalid (expired) on the destination machine.

Returning a detached license

If you wish to return the detached license before the expiration date, you can do this using the ACC on the destination machine. Find the detached license on the ACC and select 'Product'. You will be p[resented with the following

Products Host Name: chimera				
Filter by: Key:1052358274202437746 Vendor:30308				
Product Name		Vendor	Location	Actions
TacticLite	⇔	30308	Local	Cancel License Features

Select 'Cancel License'. You will then see:

Product	TacticLite (ID:9)
Vendor	30308 (ID:30308)
Sentinel Key	1052358274202437746
Expiration Date	Fri Nov 04 2022 23:59:30 GMT+0000
Parent Key	820630612125071837
License Host	No access to parent key. R2H file must be transferred manually
Current Sessions Inc	one

Select 'Cancel License' again and you will see the following

		Lice
Recipient Name		
Product	TacticLite (ID:9)	
Vendor	30308 (ID:30308)	
Sentinel Key ID	1052358274202437746	
License successf Save the R2H file a	ully cancelled offline. Ind transfer it to the recipient machine:	
Save As		
A backup of this R2 Filename: 2022110	2H file can be found in the 'cancelled' directory of the hosting License Manager. 3 134051 0001.r2h	

Save the r2h file, copy it back to the host machine and restore the licence using the Update/Attach tab on the host ACC. This will reattach the license to the host machine.

Troubleshooting

Transfer: Issues could occur when trying to transfer a software license if the correct order of events wasn't followed. Please ensure you follow the above steps and don't skip any. The most common mistake is generating the 'id' file on the source machine rather than the destination machine. If you have done this, you can re-apply the h2h file on the original machine and then repeat the process using the id from the destination machine.

Clone issues. This applies to software licenses only. If your license reports a 'clone' error then it is likely that you may have changed something in the machine, i.e. Hard disk, memory, CPU, Network controllers etc. Or you may have reinstalled the OS. It is advised that you transfer the license to another, temporary machine before upgrading, and then transfer back. Small hardware changes and OS updates do not cause an issue.

In this situation, generate a new c2v and send this to support@rtsw.co.uk. They may be able to clear the clone error and send you an update. If this fails, then we will send you an id so you can transfer the old license off and send you a new one to replace it

Out of sequence. These errors occur when there is more than one update outstanding on your license. The easiest way to resolve this is to use the online portal to update the license. If this fails - or is not possible then send a c2v to RT support and they will help you clear this error.

License failure. If you receive a message 'License not found' when you run the software, please try the following:

Hardware dongle - Replug the dongle into the USB port or try a different USB port

Software License - Check that the driver is running. Go to '<u>http://localhost:1947</u>'. You should see a page similar to the one below. If this does not appear then restart the machine

Sentinel Admin Control Center			
	Admin Control Center Help		
Sentinel Keys	Welcome to the Admin Control Center. This application enables you to manage access to software licenses and Note: You can select the language in which Admin Control Center is displayed from the bottom of the Options p		
Products	> The Admin Control Center enables you to monitor the following:		
Features	 All the Sentinel protection keys that are currently available on the network server, including their identity, 1 The number of users currently logged in to a protection key, and the maximum number of users allowed t The Features to which each protection key allows access, and any restrictions that apply to the Feature The users who are currently logged into a specific protection key, including detailed login information 		
Sessions	Note: SL UserMode keys are only displayed for the local (Windows) machine. SL UserMode keys are not displa		